Package 'AssetCorr'

January 20, 2025

Type Package

Title Estimating Asset Correlations from Default Data

Version 1.0.4 **Date** 2021-05-04

Author Maximilian Nagl [aut,cre], Yevhen Havrylenko [aut], Marius Pfeuffer [aut], Kevin Jakob [aut], Matthias Fischer [aut], Daniel Roesch [aut]

Maintainer Maximilian Nagl <maximilian.nagl@ur.de>

Description

Functions for the estimation of intra- and inter-cohort correlations in the Vasicek credit portfolio model. For intra-cohort correlations, the package covers the two method of moments estimators of Gordy (2000) <doi:10.1016/S0378-4266(99)00054-0>, the method of moments estimator of Lucas (1995) https://jfi.pm-research.com/content/4/4/76> and a Binomial approximation extension of this approach. Moreover, the maximum likelihood estimators of Gordy and Heit-

field (2010) http://elsa.berkeley.edu/~mcfadden/e242_f03/heitfield.pdf and Duellmann and Gehde-Trapp (2004) http://hdl.handle.net/10419/19729 are implemented. For inter-cohort correlations, the method of moments estimator of Bluhm and Overbeck (2003) doi:10.1007/978-3-642-59365-9_2>/Bams et al. (2016) https://doi.org/10.1007/978-3-642-59365-9_2>/Bams et al. (2016) https://doi.org/10.1007/978-3-642-59365-9_2

//papers.ssrn.com/sol3/papers.cfm?abstract_id=2676595> is provided and the maximum likelihood estimators comprise the approaches of Gordy and Heitfield (2010)/Kalkbrener and Onwunta (2010) <ISBN: 978-1906348250> and Pfeuffer et al. (2020). Bootstrap and Jackknife procedures for bias correction are included as well as the method of moments estimator of Frei and Wunsch (2018) <doi:10.21314/JCR.2017.231> for autocorrelated time series.

License GPL-3

Imports VineCopula, mvtnorm, boot, numDeriv, mvQuad, ggplot2,

Rdpack,knitr,qpdf

Suggests markdown

VignetteBuilder knitr

RdMacros Rdpack

NeedsCompilation no

Repository CRAN

Date/Publication 2021-05-05 15:30:02 UTC

2 AssetCorr-package

Contents

AssetCorr-package AssetCorr	
Index	4
interALL interCMM interCopula interCov interJDP interMLE intraALL intraAMLE intraAMM intraBeta intraCMM intraFMM intraJDP1 intraJDP2 intraMLE intraMode	1 1 10 13 2 22 22 3 3 3 3 3 4
analyze_AssetCorr	
AssetCorr-package	

Description

Functions for the estimation of intra- and inter-cohort correlations in the Vasicek credit portfolio model. For intra-cohort correlations, the package covers the two method of moments estimators of Gordy (2000) <doi:10.1016/S0378-4266(99)00054-0>, the method of moments estimator of Lucas (1995) https://jfi.pm-research.com/content/4/4/76> and a Binomial approximation extension of this approach. Moreover, the maximum likelihood estimators of Gordy and Heitfield (2010) http://elsa.berkeley.edu/~mcfadden/e242_f03/heitfield.pdf> and Duellmann and Gehde-Trapp (2004) http://hdl.handle.net/10419/19729> are implemented. For inter-cohort correlations, the method of moments estimator of Bluhm and Overbeck (2003) https://papers.ssrn.com/sol3/papers.cfm?abstract_id=2676595 is provided and the maximum likelihood estimators comprise the approaches of Gordy and Heitfield (2010)/Kalkbrener and Onwunta (2010) <ISBN: 978-1906348250> and Pfeuffer et al. (2020). Bootstrap and Jackknife procedures for bias correction are included as well as the method of moments estimator of Frei and Wunsch (2018) doi:10.21314/JCR.2017.231> for auto-correlated time series.

Details

The DESCRIPTION file:

AssetCorr-package 3

Package: AssetCorr Type: Package

Title: Estimating Asset Correlations from Default Data

Version: 1.0.4 Date: 2021-05-04

Author: Maximilian Nagl [aut,cre], Yevhen Havrylenko [aut], Marius Pfeuffer [aut], Kevin Jakob [aut], Matthias Fi

Maintainer: Maximilian Nagl <maximilian.nagl@ur.de>

Description: Functions for the estimation of intra- and inter-cohort correlations in the Vasicek credit portfolio model. For

License: GPL-3

Imports: VineCopula, mvtnorm, boot, numDeriv, mvQuad, ggplot2, Rdpack,knitr,qpdf

Suggests: markdown VignetteBuilder: knitr RdMacros: Rdpack

Index of help topics:

AssetCorr-package AssetCorr

analyze_AssetCorr Function to evaluate several default time

series simultaneously

interALL Function to use multiple estimators

simultaneously

interCMM Corrected Asymptotic Method of Moments

Estimator of Frei and Wunsch (2018)

interCopula Copula Based Maximum Likelihood Estimator

interCov Covariance Matching Estimator

interJDP Joint Default Probability Matching Estimator,

De Servigny and Renault (2002)

interMLE Binomial Maximum Likelihood Estimator intraALL Function to use multiple estimators

simultaneously

intraAMLE Asymptotic Maximum Likelihood Estimator
intraAMM Asymptotic Method of Moments Estimator
intraBeta Parametric Approach of Botha and van Vuuren

(2010) - Beta Distribution

intraCMM Corrected Asymptotic Method of Moments

Estimator of Frei and Wunsch (2018)

intraFMM Finite Sample Method of Moments Estimator intraJDP1 Joint Default Probability Matching Estimator,

Lucas (1995)

intraJDP2 Joint Default Probability Matching Estimator,

De Servigny and Renault (2002)

intraMLE Binomial Maximum Likelihood Estimator

intraMode Parametric Approach of Botha and van Vuuren

(2010) - Mode

4 AssetCorr-package

Author(s)

Maximilian Nagl [aut,cre], Yevhen Havrylenko [aut], Marius Pfeuffer [aut], Matthias Fischer [aut], Daniel Roesch [aut]

Maintainer: Maximilian Nagl <maximilian.nagl@ur.de>

References

De Servigny, A. and O. Renault: Default correlation: empirical evidence. Working Paper, Standard and Poor's: 90-94, 2003. Available at: https://www.semanticscholar.org/paper/Default-correlation% 3A-empirical-evidence-Servigny-Renault/aae251436d0e3b489951c0d38463d71106755675. Accessed: 04.05.2020

Duellmann, K. and M. Gehde-Trapp: Systematic risk in recovery rates: an empirical analysis of US corporate credit exposures. Bundesbank Series 2, Discussion Paper (2): 2004. Available at SSRN: https://papers.ssrn.com/sol3/papers.cfm?abstract_id=2793954. Accessed: 01.05.2018

Duellmann, K., J. Kuell and M. Kunisch: Estimating asset correlations from stock prices or default rates- Which method is superior? Journal of Economic Dynamics and Control 34(11): 2341-2357, 2010

Efron, B. and R. J. Tibshirani: An introduction to the bootstrap. CRC press, 1994

Pfeuffer, M., M. Nagl, M. Fischer and D. Roesch: Parameter Estimation and Bias Correction in the Vasicek Credit Portfolio Model. Journal of Risk 22(4), 2020

Frei, C. and M. Wunsch: Moment Estimators for Autocorrelated Time Series and their Application to Default Correlations. Journal of Credit Risk 14: 1-29, 2018

Gordy, M. B.: A comparative anatomy of credit risk models. Journal of Banking & Finance 24(1): 119-149, 2000

Gordy, M. B. and E. Heitfield: Small-sample estimation of models of portfolio credit risk. In Recent Advances in Financial Engineering: Proceedings of the KIER-TMU International Workshop on Financial Engineering, 2009: Otemachi, Sankei Plaza, Tokyo, 3-4 August 2009: 43-63, World Scientific, 2010

Hoese, S. and S. Huschens: Confidence intervals for asset correlations in the asymptotic single risk factor model. In Operations Research Proceedings 2010: 111-116, 2010

Kalkbrener, M. and A. Onwunta: Validating structural credit portfolio models. Model risk-identification, measurement and management. Risk Books, London: 233-261, 2010

Loeffler, G. The effects of estimation error on measures of portfolio credit risk. Journal of Banking & Finance 27(8): 1427-1453, 2003

Lucas, D. J.: Default correlation and credit analysis. The Journal of Fixed Income 4(4): 76-87, 1995

Meyer, C.: Estimation of intra-sector asset correlations. The Journal of Risk Model Validation 3(3): 47-79, 2009

Vasicek, O. A: The distribution of loan portfolio value. Risk 15(12): 160-162, 2002

analyze_AssetCorr 5

Function to evaluate several default time series simultaneously

Description

To give a first insight of several default time series, this function combines multiple estimator functions (intra and inter) and visualize the results.

Usage

```
analyze_AssetCorr(DTS,N, B=NA, DB=NA, JC=FALSE, CI_Boot=NA, Adjust=0.0001,
type="bca", Intra=c("AMM","FMM","CMM","JDP1","JDP2","MLE","AMLE","Beta","Mode"),
Inter=c("Copula","Cov","JDP","MLE"))
```

Arguments

DTS	a matrix, containing the default time series of each sector.
N	a matrix, containing the number of obligors at the beginning of the period of sector.
В	an integer, indicating how many bootstrap repetitions should be used for the single bootstrap corrected estimate (intra and inter).
DB	a combined vector, indicating how many bootstrap repetitions should be used for the inner (first entry) and outer loop (second entry) to correct the bias using the double bootstrap (intra and inter).
JC	a logical variable, indicating if the jackknife corrected estimate should be calculated (intra and inter).
CI_Boot	a number, indicating the desired confidence interval if the single bootstrap correction is specified. By default, the interval is calculated as the bootstrap corrected and accelerated confidence interval (Bca). Furthermore, the analytical confidence intervals are provided, using the same value as CI_Boot(intra and inter).
Adjust	a number, which should be added to a observed default rate of 0 or subtracted form a observed default rate of 1 (only for the intraAMLE).
type	a string, indicating the desired method to calculate the bootstrap confidence intervals. For more details see boot.ci. Studendized confidence intervals are not supported.
Intra	a combined string, indicating which intra correlation estimators should be used. All estimators are set as default.
Inter	a combined string, indicating which inter correlation estimators should be used. All estimators are set as default.

6 analyze_AssetCorr

Details

To give an first insight, the function provides an overview of the several default time series and estimates using different estimators (intra and inter) simultaneously. The plug-in estimates of the intra correlation using inter correlation methods will be estimated via intraMLE. If DB is specified, the single bootstrap corrected estimate will be calculated by using the bootstrap values of the outer loop.

Value

The returned value is a list, containing the following entries:

Estimators_Intra

Sector Number of the sector
Sector_Name Name of the sector

Estimator Name of the applied estimator

Estimate Value of the calculated estimate

Type String, which indicating corrected/non-corrected estimates

correction Name of the correction method

B Number of single bootstrap repetitions

DB Number of the double bootstrap repetitions

CI_Boot Selected two-sided bootstrap confidence interval

CI A string, indicating if the corresponding value is the upper or lower bound

Estimators_Inter

Sector_1 Number of the sector
Sector_Name_1 Name of the sector
Sector_2 Number of the sector
Sector_Name_2 Name of the sector

Estimator Name of the applied estimator to Sector_1 and Sector_2

Estimate Value of the calculated estimateto Sector_1 and Sector_2

Type String, which indicating corrected/non-corrected estimates

correction Name of the correction method

B Number of single bootstrap repetitions

DB Number of the double bootstrap repetitions

CI_Boot Selected two-sided bootstrap confidence interval

CI A string, indicating if the corresponding value is the upper or lower bound

Author(s)

Kevin Jakob

analyze_AssetCorr 7

References

Botha M, van Vuuren G (2010). "Implied asset correlation in retail loan portfolios." *Journal of Risk Management in Financial Institutions*, **3**(2), 156–173.

Chang J, Hall P (2015). "Double-bootstrap methods that use a single double-bootstrap simulation." *Biometrika*, **102**(1), 203–214.

De Servigny A, Renault O (2002). "Default correlation: empirical evidence." *Working Paper, Standard and Poors*. Available at: https://www.semanticscholar.org/paper/Default-correlation% 3A-empirical-evidence-Servigny-Renault/aae251436d0e3b489951c0d38463d71106755675.

Duellmann K, Gehde-Trapp M (2004). "Systematic risk in recovery rates: an empirical analysis of US corporate credit exposures." *Bundesbank Series* 2, *Discussion Paper*. Available at SSRN: http://hdl.handle.net/10419/19729. Accessed: 02.11.2017.

Efron B, Tibshirani RJ (1994). An introduction to the bootstrap. CRC press.

Frei C, Wunsch M (2018). "Moment Estimators for Autocorrelated Time Series and their Application to Default Correlations." *Journal of Credit Risk*, **14**, 1–29.

Gordy MB (2000). "A comparative anatomy of credit risk models." *Journal of Banking & Finance*, **24**(1), 119–149.

Gordy MB, Heitfield E (2010). "Small-sample estimation of models of portfolio credit risk." In Recent Advances in Financial Engineering: Proceedings of the KIER-TMU International Workshop on Financial Engineering, 2009: Otemachi, Sankei Plaza, Tokyo, 3-4 August 2009, 43–63.

Kalkbrener M, Onwunta A (2010). "Validating structural credit portfolio models." *Model risk - identification, measurement and management. Risk Books, London*, 233–261.

Lucas DJ (1995). "Default correlation and credit analysis." *The Journal of Fixed Income*, **4**(4), 76–87.

Meyer C (2009). "Estimation of intra-sector asset correlations." *The Journal of Risk Model Validation*, **3**(3), 47–79.

Teetor P (2011). R Cookbook: Proven recipes for data analysis, statistics, and graphics. O'Reilly Media, Inc.

See Also

intraAMM, intraFMM, intraJDP2, intraMLE, intraJDP1, intraCMM, intraMode, intraBeta, interJDP, interCopula, interCMM, interCov, interMLE, intraALL, interALL

Examples

```
library(mvtnorm)
set.seed(111)
No0=1000 #Number of obligors in each sector
Years=20
AC=0.3
PD=0.01

Psi=rmvnorm(Years,sigma=matrix(c(1,0.5,0.5,0.5,1,0.5,0.5,0.5,1),3))
PDcond1=pnorm((qnorm(PD)-sqrt(AC)*Psi[,1])/sqrt(1-AC))
PDcond2=pnorm((qnorm(PD)-sqrt(AC/2)*Psi[,2])/sqrt(1-AC/2))
```

8 defaultTimeseries

```
PDcond3=pnorm((qnorm(PD)-sqrt(AC*2)*Psi[,3])/sqrt(1-AC*2))

DTS=cbind(rbinom(Years,No0,PDcond1),rbinom(Years,No0,PDcond2),rbinom(Years,No0,PDcond3))
N=matrix(No0,nrow = Years,ncol = 3)

Output<-analyze_AssetCorr(DTS,N)

#Bootstrap Correction and CIs

Output<-analyze_AssetCorr(DTS,N,B=100,CI_Boot=0.95)

#Double Bootstrap Correction and Jackknife
Output<-analyze_AssetCorr(DTS,N,DB=c(50,50),JC=TRUE)</pre>
```

defaultTimeseries

Creating a hypothetical Default Time Series.

Description

This function return a time series of defaults.

Usage

```
defaultTimeseries(N, AC, Years, PD)
```

Arguments

N Number of obligors for each point in time.

AC Desired asset correlation.

Years Number of points in time, which corresponds to the length of the default time

series.

PD Uniform probability of default assumed for each obligor.

Details

This function can be used to draw a random default time series, assuming a specific length of the time series, number of obligors, a uniform asset correlation and a uniform probability of default.

Value

The output contains a Nx1-vector with simulated defaults for each point in time.

interALL 9

Examples

D1<-defaultTimeseries(1000,0.1,10,0.01)

interALL

Function to use multiple estimators simultaneously

Description

To give a first insight of the default time series, this function combines multiple estimator functions and visualize the results.

Usage

```
interALL(d1,n1,d2,n2,rho1,rho2, B=NA, DB=NA, JC=FALSE, CI_Boot=NA, plot=FALSE,
type="bca",Estimator=c("Copula","Cov","JDP","MLE"),show_progress=FALSE)
```

Arguments

d1	a vector, containing the default time series of sector 1.
n1	a vector, containing the number of obligors at the beginning of the period in sector 1.
d2	a vector, containing the default time series of sector 2.
n2	a vector, containing the number of obligors at the beginning of the period in sector 2.
rho1	estimated intra correlation of sector 1.
rho2	estimated intra correlation of sector 2.
В	an integer, indicating how many bootstrap repetitions should be used for the single bootstrap corrected estimate.
DB	a combined vector, indicating how many bootstrap repetitions should be used for the inner (first entry) and outer loop (second entry) to correct the bias using the double bootstrap.
JC	a logical variable, indicating if the jackknife corrected estimate should be calculated.
CI_Boot	a number, indicating the desired confidence interval if the single bootstrap correction is specified. By default, the interval is calculated as the bootstrap corrected and accelerated confidence interval (Bca). Furthermore, the analytical confidence intervals are provided, using the same value as CI_Boot.
plot	a logical variable, indicating whether a plot of the default time series and the estimates should be generated using the multiplot function of Teetor (2011).
type	a string, indicating the desired method to calculate the bootstrap confidence intervals. For more details see boot.ci. Studendized confidence intervals are not supported.
Estimator	a combined string, indicating which estimators should be used. All estimators are set as default.
show_progress	a logical variable, indicating whether a progress bar should be displayed.

10 interALL

Details

To give an first insight, the function provides an overview of the default time series and estimates using different estimators simultaneously. If DB is specified, the single bootstrap corrected estimate will be calculated by using the bootstrap values of the outer loop.

Value

The returned value is a data frame, containing the following columns:

Estimator Name of the applied estimator

Estimate Value of the calculated estimate

Type String, which indicating corrected/non-corrected estimates

correction Name of the correction method

B Number of single bootstrap repetitions

DB Number of the double bootstrap repetitions

CI_Boot Selected two-sided bootstrap confidence interval

CI A string, indicating if the corresponding value is the upper or lower bound

Author(s)

Kevin Jakob

References

Chang J, Hall P (2015). "Double-bootstrap methods that use a single double-bootstrap simulation." *Biometrika*, **102**(1), 203–214.

De Servigny A, Renault O (2002). "Default correlation: empirical evidence." *Working Paper, Standard and Poors*. Available at: https://www.semanticscholar.org/paper/Default-correlation% 3A-empirical-evidence-Servigny-Renault/aae251436d0e3b489951c0d38463d71106755675.

Duellmann K, Gehde-Trapp M (2004). "Systematic risk in recovery rates: an empirical analysis of US corporate credit exposures." *Bundesbank Series 2, Discussion Paper*. Available at SSRN: http://hdl.handle.net/10419/19729. Accessed: 02.11.2017.

Efron B, Tibshirani RJ (1994). An introduction to the bootstrap. CRC press.

Frei C, Wunsch M (2018). "Moment Estimators for Autocorrelated Time Series and their Application to Default Correlations." *Journal of Credit Risk*, **14**, 1–29.

Gordy MB (2000). "A comparative anatomy of credit risk models." *Journal of Banking & Finance*, **24**(1), 119–149.

Gordy MB, Heitfield E (2010). "Small-sample estimation of models of portfolio credit risk." In Recent Advances in Financial Engineering: Proceedings of the KIER-TMU International Workshop on Financial Engineering, 2009: Otemachi, Sankei Plaza, Tokyo, 3-4 August 2009, 43–63.

Kalkbrener M, Onwunta A (2010). "Validating structural credit portfolio models." *Model risk - identification, measurement and management. Risk Books, London*, 233–261.

Lucas DJ (1995). "Default correlation and credit analysis." *The Journal of Fixed Income*, **4**(4), 76–87.

interCMM 11

Meyer C (2009). "Estimation of intra-sector asset correlations." *The Journal of Risk Model Validation*, **3**(3), 47–79.

Teetor P (2011). R Cookbook: Proven recipes for data analysis, statistics, and graphics. O'Reilly Media, Inc.

See Also

```
intraAMM, intraFMM, intraJDP2 intraMLE, intraJDP1, intraCMM
```

Examples

```
set.seed(111)
Psi=rmvnorm(20, sigma=matrix(c(1,0.5,0.5,1),2))
PDcond1=pnorm((qnorm(0.01)-sqrt(0.05)*Psi[,1])/sqrt(1-0.05))
PDcond2=pnorm((qnorm(0.01)-sqrt(0.2)*Psi[,2])/sqrt(1-0.2))
D1=rbinom(20,1000,PDcond1)
D2=rbinom(20,1000,PDcond2)
N1=N2=rep(1000,20)
DTS=cbind(D1,D2)
N=cbind(N1,N2)
rho1=intraMLE(D1,N1)$Original
rho2=intraMLE(D2,N2)$Original
#Point Estimates
interALL(D1,N1,D2,N2,rho1,rho2, plot=TRUE)
#Bootstrap corrected estimates of all available estimators:
InterCorr=interALL(D1,N1,D2,N2,rho1,rho2, B=500, CI_Boot=0.95 , plot=TRUE, show_progress=TRUE)
#Jackknife correction
InterCorr=interALL(D1,N1,D2,N2,rho1,rho2, JC=TRUE, plot=TRUE)
#Double Bootstrap correction with 10 repetitions in the inner loop and 50 in the outer loop
InterCorr=interALL(D1,N1,D2,N2,rho1,rho2, DB=c(10,50), plot=TRUE)
```

interCMM

Corrected Asymptotic Method of Moments Estimator of Frei and Wunsch (2018)

12 interCMM

Description

This method provides analytical bias correction via Taylor series expansion. Additionally the bias due to autocorrelated default time series can be corrected. The estimated parameter is the inter correlation of the asset variables (in contrast to all other inter correlation methods of this package).

Usage

```
interCMM(d1,n1,d2,n2,rho,l=0, B=0,DB=c(0,0), JC=FALSE, CI_Boot, type="bca", plot=FALSE)
```

Arguments

d1	a vector, containing the default time series of sector 1.
n1	a vector, containing the number of obligors at the beginning of the period in sector 1.
d2	a vector, containing the default time series of sector 2.
n2	a vector, containing the number of obligors at the beginning of the period in sector 2.
rho	estimated inter asset correlation of another estimator.
1	a number, indicating how many lags of autocorrelation should be used for the correction.
В	an integer, indicating how many bootstrap repetitions should be used for the single bootstrap corrected estimate.
DB	a combined vector, indicating how many bootstrap repetitions should be used for the inner (first entry) and outer loop (second entry) to correct the bias using the double bootstrap.
JC	a logical variable, indicating if the jackknife corrected estimate should be calculated.
CI_Boot	a number, indicating the desired confidence level if the single bootstrap correction is specified. By default, the interval is calculated as the bootstrap corrected and accelerated confidence interval (Bca). Furthermore, the analytical confidence intervals are provided, using the same value as CI_Boot.
type	a string, indicating the desired method to calculate the confidence intervals. For more details see boot.ci.
plot	a logical variable, indicating whether a plot of the single bootstrap density should be generated.

Details

This function estimates the inter correlation of the asset variables. In general, the inter correlation can be estimated for the asset variables or the systematic factors. This estimator uses a inter correlation estimate of another method to correct the bias due to small sample or autocorrelation. Only one parameter (inter correlation) must be estimated. Additionally, asymptotic confidence interval can be provided, as shown by Frei and Wunsch (2018). The inter correlation of the asset variables can be transformed to the correlation of the systematic factors as follows:

interCMM 13

```
rho_Systematic = rho_Asset/sqrt(rho_1 * rho_2)
```

If DB is specified, the single bootstrap corrected estimate will be calculated using the bootstrap values of the outer loop (oValues).

Value

The returned value is a list, containing the following components (depending on the selected arguments):

Original Estimate of the original method
Bootstrap Bootstrap corrected estimate

Double_Bootstrap

Double bootstrap corrected estimate

Jackknife Jackknife corrected estimate

CI_Boot Selected two-sided bootstrap confidence interval

bValues Estimates from the bootstrap resampling

iValues Estimates from the double bootstrap resampling- inner loop oValues Estimates from the double bootstrap resampling- outer loop

References

Chang J, Hall P (2015). "Double-bootstrap methods that use a single double-bootstrap simulation." *Biometrika*, **102**(1), 203–214.

Efron B, Tibshirani RJ (1994). An introduction to the bootstrap. CRC press.

Frei C, Wunsch M (2018). "Moment Estimators for Autocorrelated Time Series and their Application to Default Correlations." *Journal of Credit Risk*, **14**, 1–29.

See Also

```
interJDP, interCopula, interMLE, interCov
```

Examples

```
d1=defaultTimeseries(1000,0.1,10,0.01)
d2=defaultTimeseries(1000,0.2,10,0.01)
n1=n2=rep(1000,10)

#Using the Covariance method to estimate the plug-in inter correlation.
inter_sys=interCov(d1,n1,d2,n2,0.1,0.2)$Original
inter_asset= inter_sys*sqrt(0.1*0.2)

interCMM(d1,n1,d2,n2,inter_asset,l=0)

InterCorr=interCMM(d1,n1,d2,n2,inter_asset, JC=TRUE)
InterCorr=interCMM(d1,n1,d2,n2,inter_asset, B=1000, CI_Boot=0.95, plot=TRUE)
```

14 interCopula

```
InterCorr=interCMM(d1,n1,d2,n2,inter_asset, DB=c(10,50))
```

 $inter {\tt Copula}$

Copula Based Maximum Likelihood Estimator

Description

The inter correlation parameter can be estimated by fitting a Gaussian copula with Vasicek distributed margins on two observed default rate time series. The estimated parameter is the inter correlation of the systematic factors.

Usage

```
interCopula(df1, df2, B = 0, DB=c(0,0),JC = FALSE,
  CI, CI_Boot, type="bca", plot=FALSE)
```

Arguments

df1	a vector, containing the default rate time series of sector 1.
df2	a vector, containing the default rate times eries of sector 2.
В	an integer, indicating how many bootstrap repetitions should be used for the single bootstrap corrected estimate.
DB	a combined vector, indicating how many bootstrap repetitions should be used for the inner (first entry) and outer loop (second entry) to correct the bias using the double bootstrap.
JC	a logical variable, indicating if the jackknife corrected estimate should be calculated.
CI	a number, indicating the desired asymptotic confidence interval of the estimate.
CI_Boot	a number, indicating the desired bootstrap confidence interval if the single bootstrap correction is specified. By default, the interval is calculated as the bootstrap corrected and accelerated confidence interval (Bca). Furthermore, the analytical confidence intervals are provided, using the same value as CI_Boot.
type	
3.	a string, indicating the desired method to calculate the confidence intervals. For more details see $boot.ci$.
plot	

interCopula 15

Details

This function estimates the inter correlation of the systematic factors. In general the inter correlation can be estimated for the asset variables or the systematic factors. This method estimates the inter correlation of the systematic factors. The parameter will be estimated via Maximum Likelihood estimation, which ensures that an asymptotic confidence interval can be provided. The inter correlation of the systematic factors can be transformed to the correlation of the asset variables as follows:

```
rho_Asset = rho_Systematic * sqrt(rho_1 * rho_2)
```

The estimated inter correlation of the systematic factors lies between -1 and 1. If DB is specified, the single bootstrap corrected estimate will be calculated using the bootstrap values of the outer loop (oValues).

Value

The returned value is a list, containing the following components (depending on the selected arguments):

Original Estimate of the original method

Bootstrap Bootstrap corrected estimate

Double_Bootstrap

Double bootstrap corrected estimate

Jackknife Jackknife corrected estimate

CI Selected two-sided asymptotic bootstrap confidence interval

CI_Boot Selected two-sided bootstrap confidence interval

bValues Estimates from the bootstrap resampling

iValues Estimates from the double bootstrap resampling- inner loop oValues Estimates from the double bootstrap resampling- outer loop

References

Chang J, Hall P (2015). "Double-bootstrap methods that use a single double-bootstrap simulation." *Biometrika*, **102**(1), 203–214.

Efron B, Tibshirani RJ (1994). An introduction to the bootstrap. CRC press.

Pfeuffer M, Nagl M, Fischer M, Roesch D (2020). "Parameter Estimation and Bias Correction in the Vasicek Credit Portfolio Model." *Journal of Risk*, **22number**.

See Also

```
interJDP, interCMM, interMLE, interCov
```

16 interCov

Examples

```
set.seed(10)
d1=defaultTimeseries(1000,0.1,10,0.01)
d2=defaultTimeseries(1000,0.2,10,0.01)
n=rep(1000,10)

df1=d1/n
df2=d2/n

InterCorr=interCopula(df1,df2, CI=0.95)

InterCorr=interCopula(df1,df2, JC=TRUE)

InterCorr=interCopula(df1,df2, B=1000, CI_Boot=0.95, plot=TRUE)
InterCorr=interCopula(df1,df2, DB=c(50,50))
```

interCov

Covariance Matching Estimator

Description

The inter correlation parameter can be estimated by matching the empirical covariance of two default time series with the theoretical. The estimated parameter is the inter correlation of the systematic factors.

Usage

```
interCov(d1, n1, d2, n2, rho1, rho2, B = 0, DB=c(0,0), JC = FALSE,
CI_Boot, type="bca", plot=FALSE)
```

Arguments

d1	a vector, containing the default time series of sector 1.
n1	a vector, containing the number of obligors at the beginning of the period in sector 1.
d2	a vector, containing the default times eries of sector 2.
n2	a vector, containing the number of obligors at the beginning of the period in sector 2.
rho1	estimated intra asset correlation of sector 1.
rho2	estimated intra asset correlation of sector 2.
В	an integer, indicating how many bootstrap repetitions should be used for the single bootstrap corrected estimate.

interCov 17

DB	a combined vector, indicating how many bootstrap repetitions should be used for the inner (first entry) and outer loop (second entry) to correct the bias using the double bootstrap.
JC	a logical variable, indicating if the jackknife corrected estimate should be calculated.
CI_Boot	a number, indicating the desired confidence level if the single bootstrap correction is specified. By default, the interval is calculated as the bootstrap corrected and accelerated confidence interval (Bca).
type	a string indicating the desired method to calculate the confidence intervals. For more details see boot.ci.
plot	a logical variable, indicating whether a plot of the single bootstrap density should be generated.

Details

This function estimates the inter correlation of the systematic factors. In general, the inter correlation can be estimated for the asset variables or the systematic factors. To ensure the traceability of the estimation, the intra correlation estimates will be used as plug-in estimates. Hence only one parameter (inter correlation) must be estimated. The inter correlation of the systematic factors can be transformed to the correlation of the asset variables as follows:

$$rho_Asset = rho_Systematic * sqrt(rho_1 * rho_2)$$

The estimated inter correlation of the systematic factors lies between -1 and 1.

If DB is specified, the single bootstrap corrected estimate will be calculated using the bootstrap values of the outer loop (oValues).

Value

The returned value is a list, containing the following components (depending on the selected arguments):

Original	Estimate of the original method
Bootstrap	Bootstrap corrected estimate
Double_Bootstra	q
	Double bootstrap corrected estimate
Jackknife	Jackknife corrected estimate
CI_Boot	Selected two-sided bootstrap confidence interval
bValues	Estimates from the single bootstrap resampling
iValues	Estimates from the double bootstrap resampling- inner loop
oValues	Estimates from the double bootstrap resampling- outer loop

18 interJDP

References

Chang J, Hall P (2015). "Double-bootstrap methods that use a single double-bootstrap simulation." *Biometrika*, **102**(1), 203–214.

Bluhm C, Overbeck L (2003). "Systematic risk in homogeneous credit portfolios." *Credit risk. Physica-Verlag, Heidelberg*, 35–48.

Efron B, Tibshirani RJ (1994). An introduction to the bootstrap. CRC press.

See Also

```
interJDP, interCMM, interMLE, interCopula
```

Examples

```
set.seed(10)
d1=defaultTimeseries(1000,0.1,10,0.01)
d2=defaultTimeseries(1000,0.2,10,0.01)
n1=n2=rep(1000,10)

InterCorr=interCov(d1,n1,d2,n2,0.1,0.2)

InterCorr=interCov(d1,n1,d2,n2,0.1,0.2, JC=TRUE)
InterCorr=interCov(d1,n1,d2,n2,0.1,0.2, B=1000, CI_Boot=0.95)

InterCorr=interCov(d1,n1,d2,n2,0.1,0.2, DB=c(50,50))
```

interJDP

Joint Default Probability Matching Estimator, De Servigny and Renault (2002)

Description

The inter correlation parameter can be estimated by matching the empirical Joint Default Probability of two default time series with the theoretical one. The estimated parameter is the correlation of the systematic factors.

Usage

```
interJDP(d1, n1, d2, n2, rho1, rho2, B = 0, DB=c(0,0), JC = FALSE, CI\_Boot, type="bca", plot=FALSE)
```

interJDP 19

Arguments

d1	a vector, containing the default time series of sector 1.
n1	a vector, containing the number of obligors at the beginning of the period in sector $1. $
d2	a vector, containing the default time series of sector 2.
n2	a vector, containing the number of obligors at the beginning of the period in sector 2 .
rho1	estimated intra correlation of sector 1.
rho2	estimated intra correlation of sector 2.
В	an integer, indicating how many bootstrap repetitions should be used for the single bootstrap corrected estimate.
DB	a combined vector, indicating how many bootstrap repetitions should be used for the inner (first entry) and outer loop (second entry) to correct the bias using the double bootstrap.
JC	a logical variable, indicating if the jackknife corrected estimate should be calculated.
CI_Boot	a number, indicating the desired confidence level if the single bootstrap correction is specified. By default, the interval is calculated as the bootstrap corrected and accelerated confidence interval (Bca).
type	a string, indicating the desired method to calculate the confidence intervals. For more details see $boot.ci.$
plot	a logical variable, indicating whether a plot of the single bootstrap density should be generated.

Details

This function estimates the inter correlation of the systematic factor. In general, the inter correlation can be estimated for the asset variables or the systematic factors. To ensure the traceability of the estimation, the intra correlation estimates will be used as plug-in estimates. Hence only one parameter (inter correlation) must be estimated. The inter correlation of the systematic factor can be transformed to the correlation of the asset variables as follows:

$$rho_Asset = rho_Systematic * sqrt(rho_1 * rho_2)$$

The estimated inter correlation of the systematic factors lies between -1 and 1.

If DB is specified, the single bootstrap corrected estimate will be calculated using the bootstrap values of the outer loop (oValues).

Value

The returned value is a list, containing the following components (depending on the selected arguments):

Original Estimate of the original method

20 interJDP

Bootstrap Bootstrap corrected estimate

Double_Bootstrap

Double bootstrap corrected estimate

Jackknife Jackknife corrected estimate

CI_Boot Selected two-sided bootstrap confidence interval

bValues Estimates from the bootstrap resampling

iValues Estimates from the double bootstrap resampling- inner loop oValues Estimates from the double bootstrap resampling- outer loop

References

Chang J, Hall P (2015). "Double-bootstrap methods that use a single double-bootstrap simulation." *Biometrika*, **102**(1), 203–214.

De Servigny A, Renault O (2002). "Default correlation: empirical evidence." *Working Paper, Standard and Poors*. Available at: https://www.semanticscholar.org/paper/Default-correlation% 3A-empirical-evidence-Servigny-Renault/aae251436d0e3b489951c0d38463d71106755675.

Efron B, Tibshirani RJ (1994). An introduction to the bootstrap. CRC press.

Kalkbrener M, Onwunta A (2010). "Validating structural credit portfolio models." *Model risk - identification, measurement and management. Risk Books, London*, 233–261.

See Also

```
interCov, interCMM, interMLE, interCopula
```

Examples

```
d1=defaultTimeseries(1000,0.1,10,0.01)
d2=defaultTimeseries(1000,0.2,10,0.01)
n1=n2=rep(1000,10)

InterCorr=interJDP(d1,n1,d2,n2,0.1,0.2)

InterCorr=interJDP(d1,n1,d2,n2,0.1,0.2, JC=TRUE)
InterCorr=interJDP(d1,n1,d2,n2,0.1,0.2, B=1000, CI_Boot=0.95)

InterCorr=interJDP(d1,n1,d2,n2,0.1,0.2, DB=c(10,50))
```

interMLE 21

interMLE	Binomial Maximum Likelihood Estimator

Description

The inter correlation parameter can be estimated by maximizing the Vasicek-binomial log-likelihood. The default process in the Vasicek model follows a binomial distribution, conditional on the realisation of the systematic factor. Hence, the inter correlation of the systematic factor can be estimated by maximizing the resulting log likelihood.

Usage

```
interMLE(d1, n1, d2, n2, rho1, rho2, B = 0, DB=c(0,0), JC = FALSE, CI, plot=FALSE)
```

Arguments

d1	a vector, containing the default time series of sector 1.
n1	a vector, containing the number of obligors at the beginning of the period in sector 1.
d2	a vector, containing the default time series of sector 2.
n2	a vector, containing the number of obligors at the beginning of the period in sector 2.
rho1	estimated intra correlation of sector 1.
rho2	estimated intra correlation of sector 2.
В	an integer, indicating how many bootstrap repetitions should be used for the single bootstrap corrected estimate.
DB	a combined vector, indicating how many bootstrap repetitions should be used for the inner (first entry) and outer loop (second entry) to correct the bias using the double bootstrap.
JC	a logical variable, indicating if the jackknife corrected estimate should be calculated.
CI	a number, indicating the desired asymptotic confidence bound of the estimate.
plot	a logical variable, indicating whether a plot of the single bootstrap density should be generated.

Details

This function estimates the inter correlation of the systematic factor. In general, the inter correlation can be estimated for the asset variables or the systematic factors. To ensure the traceability of the estimation, the intra correlation estimates will be used as plug-in estimates. Hence only one parameter (inter correlation) must be estimated. The inter correlation of the systematic factor can be transformed to the correlation of the asset variables as follows:

22 interMLE

```
rho_Asset = rho_Systematic * sqrt(rho_1 * rho_2)
```

The estimated inter correlation of the systematic factors lies between -1 and 1.

If DB is specified, the single bootstrap corrected estimate will be calculated using the bootstrap values of the outer loop (oValues).

Value

The returned value is a list, containing the following components (depending on the selected arguments):

Original Estimate of the original method
Bootstrap Bootstrap corrected estimate

Double_Bootstrap

Double bootstrap corrected estimate

Jackknife Jackknife corrected estimate

CI Selected two-sided asymptotic bootstrap confidence interval

CI_Boot Selected two-sided bootstrap confidence interval

bValues Estimates from the bootstrap resampling

iValues Estimates from the double bootstrap resampling- inner loop oValues Estimates from the double bootstrap resampling- outer loop

References

Chang J, Hall P (2015). "Double-bootstrap methods that use a single double-bootstrap simulation." *Biometrika*, **102**(1), 203–214.

Efron B, Tibshirani RJ (1994). An introduction to the bootstrap. CRC press.

Gordy MB, Heitfield E (2010). "Small-sample estimation of models of portfolio credit risk." In Recent Advances in Financial Engineering: Proceedings of the KIER-TMU International Workshop on Financial Engineering, 2009: Otemachi, Sankei Plaza, Tokyo, 3-4 August 2009, 43–63.

See Also

```
interJDP, interCopula, interCMM, interCov
```

Examples

```
d1=defaultTimeseries(1000,0.1,10,0.01)
d2=defaultTimeseries(1000,0.2,10,0.01)
n1=n2=rep(1000,10)

InterCorr=interMLE(d1,n1,d2,n2,0.1,0.2, CI=0.95)
InterCorr=interMLE(d1,n1,d2,n2,0.1,0.2, JC=TRUE)
```

intraALL 23

```
InterCorr=interMLE(d1,n1,d2,n2,0.1,0.2, B=1000, CI_Boot=0.95)
InterCorr=interMLE(d1,n1,d2,n2,0.1,0.2, DB=c(10,50))
```

intraALL

Function to use multiple estimators simultaneously

Description

To give a first insight of the default time series, this function combines multiple estimator functions and visualize the results.

Usage

```
intraALL(d,n, B=NA, DB=NA, JC=FALSE, CI_Boot=NA, Adjust=0.0001, plot=FALSE,
type="bca", Quantile=0.999, Estimator=c("AMM","FMM","CMM","JDP1","JDP2",
"MLE","AMLE","Beta","Mode"),show_progress=FALSE)
```

Arguments

d	a vector, containing the default time series of the sector.
n	a vector, containing the number of obligors at the beginning of the period in the sector.
В	an integer, indicating how many bootstrap repetitions should be used for the single bootstrap corrected estimate.
DB	a combined vector, indicating how many bootstrap repetitions should be used for the inner (first entry) and outer loop (second entry) to correct the bias using the double bootstrap.
JC	a logical variable, indicating if the jackknife corrected estimate should be calculated.
CI_Boot	a number, indicating the desired confidence interval if the single bootstrap correction is specified. By default, the interval is calculated as the bootstrap corrected and accelerated confidence interval (Bca). Furthermore, the analytical confidence intervals are provided, using the same value as CI_Boot.
Adjust	a number, which should be added to a observed default rate of 0 or subtracted form a observed default rate of 1 (only for the AMLE).
plot	a logical variable, indicating whether a plot of the default time series and the estimates should be generated using the multiplot function of Teetor (2011).
type	a string, indicating the desired method to calculate the bootstrap confidence intervals. For more details see boot.ci. Studendized confidence intervals are not supported.

24 intraALL

Quantile a number, indicating the desired confidence level of the Value-at-Risk (only for

the intraBeta).

Estimator a combined string, indicating which estimators should be used. All estimators

are set as default.

show_progress a logical variable, indicating whether a progress bar should be displayed.

Details

To give an first insight, the function provides an overview of the default time series and estimates using different estimators simultaneously. If DB is specified, the single bootstrap corrected estimate will be calculated by using the bootstrap values of the outer loop.

Value

The returned value is a data frame, containing the following columns:

Estimator Name of the applied estimator

Estimate Value of the calculated estimate

Type String, which indicating corrected/non-corrected estimates

correction Name of the correction method

B Number of single bootstrap repetitions

DB Number of the double bootstrap repetitions

CI_Boot Selected two-sided bootstrap confidence interval

CI A string, indicating if the corresponding value is the upper or lower bound

Author(s)

Kevin Jakob

References

Chang J, Hall P (2015). "Double-bootstrap methods that use a single double-bootstrap simulation." *Biometrika*, **102**(1), 203–214.

De Servigny A, Renault O (2002). "Default correlation: empirical evidence." *Working Paper, Standard and Poors*. Available at: https://www.semanticscholar.org/paper/Default-correlation% 3A-empirical-evidence-Servigny-Renault/aae251436d0e3b489951c0d38463d71106755675.

Duellmann K, Gehde-Trapp M (2004). "Systematic risk in recovery rates: an empirical analysis of US corporate credit exposures." *Bundesbank Series 2, Discussion Paper*. Available at SSRN: http://hdl.handle.net/10419/19729. Accessed: 02.11.2017.

Efron B, Tibshirani RJ (1994). An introduction to the bootstrap. CRC press.

Frei C, Wunsch M (2018). "Moment Estimators for Autocorrelated Time Series and their Application to Default Correlations." *Journal of Credit Risk*, **14**, 1–29.

Gordy MB (2000). "A comparative anatomy of credit risk models." *Journal of Banking & Finance*, **24**(1), 119–149.

Gordy MB, Heitfield E (2010). "Small-sample estimation of models of portfolio credit risk." In Recent Advances in Financial Engineering: Proceedings of the KIER-TMU International Workshop on Financial Engineering, 2009: Otemachi, Sankei Plaza, Tokyo, 3-4 August 2009, 43–63.

Kalkbrener M, Onwunta A (2010). "Validating structural credit portfolio models." *Model risk - identification, measurement and management. Risk Books, London*, 233–261.

Lucas DJ (1995). "Default correlation and credit analysis." *The Journal of Fixed Income*, **4**(4), 76–87.

Meyer C (2009). "Estimation of intra-sector asset correlations." *The Journal of Risk Model Validation*, **3**(3), 47–79.

Teetor P (2011). R Cookbook: Proven recipes for data analysis, statistics, and graphics. O'Reilly Media, Inc.

See Also

intraAMM, intraFMM, intraJDP2, intraMLE, intraJDP1, intraCMM, intraMode,intraBeta

Examples

```
set.seed(10)
d=defaultTimeseries(1000,0.01,20,0.01)
n=rep(1000,20)

#Point Estimate of all available estimators:
intraALL(d,n,Adjust=0.001, plot=TRUE)

#Bootstrap corrected estimates of all available estimators:
IntraCorr=intraALL(d,n, Adjust=0.001, B=500, CI_Boot=0.95, plot=TRUE, show_progress=TRUE)

#Select some estimators
IntraCorr=intraALL(d,n,B=500, CI_Boot=0.95, Adjust=0.001, Estimator=c("AMM","FMM"), plot=TRUE)

#Jackknife correction
IntraCorr=intraALL(d,n, JC=TRUE,Adjust=0.001, plot=TRUE)

#Double Bootstrap correction with 10 repetitions in the inner loop and 50 in the outer loop
IntraCorr=intraALL(d,n, DB=c(10,50),Adjust=0.001, plot=TRUE)
```

Description

This estimator is based on the assumption of infinitely large portfolio size and a sufficient length of the default time series. In the asymptotic case, neither the default rate of 0 or a 1 occur. Hence one has to make an adjustment in these cases.

Usage

```
intraAMLE(d, n, B = 0, DB=c(0,0),JC = FALSE, Adjust = 0, CI_1,CI_2, CI_Boot,VaR=0.99, VaR_CI=0.95, ES=0.975, ES_CI=0.95, type="bca", plot=FALSE)
```

Arguments

d	a vector, containing the default time series of the sector.
n	a vector, containing the number of obligors at the beginning of the period in the sector.
В	an integer, indicating how many bootstrap repetitions should be used for the single bootstrap corrected estimate.
DB	a combined vector, indicating how many bootstrap repetitions should be used for the inner (first entry) and outer loop (second entry) to correct the bias using the double bootstrap.
JC	a logical variable, indicating if the jackknife corrected estimate should be calculated.
Adjust	a number, which should be added to a observed default rate of 0 or subtracted form a observed default rate of 1.
CI_1	a number, indicating the desired analytical confidence interval of the estimate. The interval is computed by asymptotic Cramer-Rao lower bound for the standard deviation of the estimate based on Duellmann and Gehde-Trapp (2004). Additionally the asymptotic confidence interval for the unconditional PD is computed.
CI_2	a number, indicating the desired analytical confidence interval of the estimate. The interval is computed by constructing a confidence interval for the variance, which can be transferred to the estimate based on Hoese and Huschens (2011).
CI_Boot	a number, indicating the desired confidence interval if the single bootstrap correction is specified. By default, the interval is calculated as the bootstrap corrected and accelerated confidence interval (Bca). Furthermore, the analytical confidence intervals are provided, using the same value as CI_Boot.
VaR	a number, indicating the desired confidence level for the asymptotic Value-at-Risk.
VaR_CI	a number, indicating the desired confidence interval for the asymptotic Value-at-Risk, derived by the delta method.
ES	a number, indicating the desired confidence level for the asymptotic Expected Shortfall.
ES_CI	a number, indicating the desired confidence interval for the asymptotic Expected Shortfall, derived by the delta method.

type a string, indicating the desired method to calculate the confidence intervals. For

more details see boot.ci.

plot a logical variable, indicating whether a plot of the single bootstrap density should

be generated.

Details

This estimator is based on the asymptotic assumptions of the Vasicek model, especially the assumption of an infinite large portfolio. If a 0 or 1 occurs at least once in the default rate time series, the estimator can not converge. Therefore, an adjustment (Adjust) can be made. Nevertheless, Meyer (2009) argued that the adjustment can harm the estimation efficiency.

Additionally two different asymptotic confidence intervals are provided. Bootstrap and jackknife corrections are also possible. If DB is specified, the single bootstrap corrected estimate will be calculated using the bootstrap values of the outer loop (oValues).

Value

The returned value is a list, containing the following components (depending on the selected arguments):

PD Estimate of the unconditional PD based on Duellmann and Gehde-Trapp (2004)

PD_CI_1 [Two-sided asymptotic confidence interval for the unconditional PD based on

Duellmann and Gehde-Trapp (2004)

Original Estimate of the original method

Bootstrap Bootstrap corrected estimate

Double_Bootstrap

Double bootstrap corrected estimate

Jackknife Jackknife corrected estimate

CI_1 Selected two-sided asymptotic confidence interval based on Duellmann and Gehde-

Trapp (2004)

CI_2 Selected two-sided asymptotic confidence interval based on Hoese and Huschens

(2011)

CI_Boot Selected two-sided bootstrap confidence interval

VaR Asymptotic Value-at-Risk

VaR_CI Confidence interval for the asymptotic Value-at-Risk

ES Asymptotic Expected Shortfall

ES_CI Confidence interval for the asymptotic Expected Shortfall

bValues Estimates from the single bootstrap resampling

iValues Estimates from the double bootstrap resampling- inner loop oValues Estimates from the double bootstrap resampling- outer loop

References

Chang J, Hall P (2015). "Double-bootstrap methods that use a single double-bootstrap simulation." *Biometrika*, **102**(1), 203–214.

Duellmann K, Gehde-Trapp M (2004). "Systematic risk in recovery rates: an empirical analysis of US corporate credit exposures." *Bundesbank Series* 2, *Discussion Paper*. Available at SSRN: http://hdl.handle.net/10419/19729. Accessed: 02.11.2017.

Efron B, Tibshirani RJ (1994). An introduction to the bootstrap. CRC press.

Hoese S, Huschens S (2011). "Confidence intervals for asset correlations in the asymptotic single risk factor model." In *Operations Research Proceedings* 2010, 111–116. Springer.

Meyer C (2009). "Estimation of intra-sector asset correlations." *The Journal of Risk Model Validation*, **3**(3), 47–79.

Pfeuffer M, Nagl M, Fischer M, Roesch D (2020). "Parameter Estimation and Bias Correction in the Vasicek Credit Portfolio Model." *Journal of Risk*, **22number**.

See Also

intraAMM, intraFMM, intraJDP2, intraMLE, intraJDP1, intraCMM, intraMode,intraBeta

Examples

```
set.seed(10)
d=defaultTimeseries(100,0.01,10,0.01)
n=rep(100,10)
#Sensitivity to the adjustment
intraAMLE(d,n,Adjust=0.001)
intraAMLE(d,n,Adjust=0.0001)
#Estimation with confidence intervals- I
IntraCorr=intraAMLE(d,n, Adjust=0.001, CI_1=0.95 )
#Estimation with confidence intervals- II
IntraCorr=intraAMLE(d,n, Adjust=0.001, CI_2=0.95 )
#Jackknife correction
IntraCorr=intraAMLE(d,n,Adjust=0.001, JC=TRUE)
#Bootstrap correction with bootstrap confidence intervals
IntraCorr=intraAMLE(d,n, Adjust=0.001, B=1000, CI_Boot=0.95 )
#Bootstrap correction with bootstrap confidence intervals and plot
IntraCorr=intraAMLE(d,n, B=1000, Adjust=0.001, CI_Boot=0.95, plot=TRUE )
#Double Bootstrap correction with 10 repetitions in the inner loop and 50 in the outer loop
IntraCorr=intraAMLE(d,n,Adjust=0.001, DB=c(10,50))
```

intraAMM 29

intraAMM	Asymptotic Method of Moments Estimator	

Description

The intra asset correlation will be estimated by fitting the first two moments of the default rate time series to the theoretical moments of the default rate and backing out the remaining correlation parameter numerically. Additionally, bootstrap and jackknife corrections are implemented.

Usage

```
intraAMM(d, n, B = 0, DB=c(0,0), JC = FALSE,CI_Boot, type="bca", plot=FALSE)
```

Arguments

d	a vector, containing the default time series of the sector.
n	a vector, containing the number of obligors at the beginning of the period over time.
В	an integer, indicating how many bootstrap repetitions should be used for the single bootstrap corrected estimate.
DB	a combined vector, indicating how many bootstrap repetitions should be used for the inner (first entry) and outer loop (second entry) to correct the bias using the double bootstrap.
JC	a logical variable, indicating if the jackknife corrected estimate should be calculated.
CI_Boot	a number, indicating the desired confidence interval if the single bootstrap correction is specified. By default, the interval is calculated as the bootstrap corrected and accelerated confidence interval (Bca).
type	a string, indicating the desired method to calculate the bootstrap confidence intervals. For more details see boot.ci. Studendized confidence intervals are not supported.
plot	a logical variable, indicating whether a plot of the single bootstrap density should be generated.

Details

As stated by Vasicek (1991) and Vasicek (2002), the asset variables follow a bivariate normal distribution. Since this distribution can be parametrized by the first two moments, namely the expected value and the variance, the remaining correlation parameter can be backed out numerically. The expected value will be approximated by the mean of the default rate and the variance is defined as the sample variance of the default rate. For theoretical background, see Gordy (2000). If DB is specified, the single bootstrap corrected estimate will be calculated by using the bootstrap values of the outer loop (oValues).

30 intraAMM

Value

The returned value is a list, containing the following components (depending on the selected arguments):

Original Estimate of the original method
Bootstrap Bootstrap corrected estimate

Double_Bootstrap

Double bootstrap corrected estimate

Jackknife Jackknife corrected estimate

CI_Boot Selected two-sided bootstrap confidence interval

bValues Estimates from the bootstrap resampling

iValues Estimates from the double bootstrap resampling- inner loop oValues Estimates from the double bootstrap resampling- outer loop

References

Chang J, Hall P (2015). "Double-bootstrap methods that use a single double-bootstrap simulation." *Biometrika*, **102**(1), 203–214.

Efron B, Tibshirani RJ (1994). An introduction to the bootstrap. CRC press.

Gordy MB (2000). "A comparative anatomy of credit risk models." *Journal of Banking & Finance*, **24**(1), 119–149.

Vasicek O (1991). "Limiting loan loss probability distribution." *Finance, Economics and Mathematics*, 147–148.

Vasicek O (2002). "The distribution of loan portfolio value." Risk, 15(12), 160–162.

See Also

intraFMM, intraJDP1, intraJDP2, intraCMM, intraMLE, intraAMLE, intraMode,intraBeta

Examples

```
set.seed(111)
d=defaultTimeseries(1000,0.3,20,0.01)
n=rep(1000,20)

IntraCorr=intraAMM(d,n)

#Jackknife correction
IntraCorr=intraAMM(d,n, JC=TRUE)

#Bootstrap correction with confidence intervals
IntraCorr=intraAMM(d,n, B=1000, CI_Boot=0.95 )

#Bootstrap correction with confidence intervals and plot
IntraCorr=intraAMM(d,n, B=1000, CI_Boot=0.95, plot=TRUE )
```

intraBeta 31

#Double Bootstrap correction with 10 repetitions in the inner loop and 50 in the outer loop IntraCorr=intraAMM(d,n, DB=c(10,50))

intraBeta Parametric Approach of Botha and van Vuuren (2010)- Beta Distribution	intraBeta	
---	-----------	--

Description

The intra asset correlation will be estimated by fitting a beta distribution onto the default rate time series, then calculating the Value-at-Risk (VaR) of this beta distribution and fit it to the theoretical VaR of the Vasicek distribution. The correlation parameter will be backed out numerically. Additionally, bootstrap and jackknife corrections are implemented.

Usage

```
intraBeta(d, n, Quantile=0.999,B = 0, DB=c(0,0), JC = FALSE, CI_Boot, type="bca", plot=FALSE)
```

Arguments

d	a vector, containing the default time series of the sector.
n	a vector, containing the number of obligors at the beginning of the period over time.
Quantile	a number, indicating the desired confidence level of the Value-at-Risk.
В	an integer, indicating how many bootstrap repetitions should be used for the single bootstrap corrected estimate.
DB	a combined vector, indicating how many bootstrap repetitions should be used for the inner (first entry) and outer loop (second entry) to correct the bias using the double bootstrap.
JC	a logical variable, indicating if the jackknife corrected estimate should be calculated.
CI_Boot	a number, indicating the desired confidence interval if the single bootstrap correction is specified. By default, the interval is calculated as the bootstrap corrected and accelerated confidence interval (Bca).
type	a string, indicating the desired method to calculate the bootstrap confidence intervals. For more details see boot.ci. Studendized confidence intervals are not supported.
plot	a logical variable, indicating whether a plot of the single bootstrap density should be generated.

32 intraBeta

Details

As stated by Botha and van Vuuren (2010) one can estimate the intra correlation by matching VaR of a parametrized beta distribution onto the VaR of the Vasicek distribution. To do so, the shape parameters (alpha and beta) of the beta distribution are estimated according to Botha and van Vuuren (2010). Afterwards, the VaR_Beta at the confidence level of Quantile will be estimated. In a third step, this VaR_Beta is matched with the theoretical VaR of the Vasicek distribution, given by Vasicek (1991):

$$VaR_Vasicek = Phi((Phi^-1(PD) + sqrt(rho) * Phi^-1(Quantile))/sqrt(1 - rho))$$

Since Quantile and the corresponding VaR_Beta is known, the intra correlation parameter can be backed out numerically. This estimator is sensitive to the chosen Quantile. Botha and van Vuuren (2010) suggested to use Quantile=0.999, but for validation purposes one may choose different values of Quantile to infer information about the robustness of the correlation estimate.

If DB is specified, the single bootstrap corrected estimate will be calculated by using the bootstrap values of the outer loop (oValues).

Value

The returned value is a list, containing the following components (depending on the selected arguments):

Original Estimate of the original method
Bootstrap Bootstrap corrected estimate

Double_Bootstrap

Double bootstrap corrected estimate

Jackknife Jackknife corrected estimate

CI_Boot Selected two-sided bootstrap confidence interval

bValues Estimates from the bootstrap resampling

iValues Estimates from the double bootstrap resampling- inner loop oValues Estimates from the double bootstrap resampling- outer loop

References

Botha M, van Vuuren G (2010). "Implied asset correlation in retail loan portfolios." *Journal of Risk Management in Financial Institutions*, **3**(2), 156–173.

Chang J, Hall P (2015). "Double-bootstrap methods that use a single double-bootstrap simulation." *Biometrika*, **102**(1), 203–214.

Efron B, Tibshirani RJ (1994). An introduction to the bootstrap. CRC press.

Gordy MB (2000). "A comparative anatomy of credit risk models." *Journal of Banking & Finance*, **24**(1), 119–149.

Vasicek O (1991). "Limiting loan loss probability distribution." *Finance, Economics and Mathematics*, 147–148.

intraCMM 33

See Also

intraFMM, intraJDP1, intraJDP2 intraCMM, intraMLE, intraAMLE intraMode

Examples

```
set.seed(111)
d=defaultTimeseries(1000,0.3,20,0.01)
n=rep(1000,20)

IntraCorr=intraBeta(d,n)

#Jackknife correction
IntraCorr=intraBeta(d,n, JC=TRUE)

#Bootstrap correction with confidence intervals
IntraCorr=intraBeta(d,n, B=1000, CI_Boot=0.95)

#Bootstrap correction with confidence intervals and plot
IntraCorr=intraBeta(d,n, B=1000, CI_Boot=0.95, plot=TRUE)

#Double Bootstrap correction with 10 repetitions in the inner loop and 50 in the outer loop
IntraCorr=intraBeta(D1,N1, DB=c(10,50))
```

intraCMM

Corrected Asymptotic Method of Moments Estimator of Frei and Wunsch (2018)

Description

The estimator is based on Frei and Wunsch (2018), who introduced an analytic bias correction via Taylor series expansion. Additionally, the bias due to autocorrelated default time series can be corrected. Furthermore, additional bootstrap and jackknife bias corrections are implemented.

Usage

```
intraCMM(d,n,l=0, B=0, DB=c(0,0), JC=FALSE, CI_Boot,type="bca", plot=FALSE)
```

Arguments

d a vector, containing the default time series of the se	ector.
--	--------

n a vector, containing the number of obligors at the beginning of the period in the

sector.

a number, indicating how many lags of autocorrelation should be used for the

correction.

34 intraCMM

В an integer, indicating how many bootstrap repetitions should be used for the single bootstrap corrected estimate. DB a combined vector, indicating how many bootstrap repetitions should be used for the inner (first entry) and outer loop (second entry) to correct the bias using the double bootstrap. JC. a logical variable, indicating if the jackknife corrected estimate should be calculated. CI Boot a number, indicating the desired confidence level if the single bootstrap correction is specified. By default, the interval is calculated as the bootstrap corrected and accelerated confidence interval (Bca). Furthermore, the analytical confidence intervals are provided, using the same value as CI_Boot. a string, indicating the desired method to calculate the confidence intervals. For type more details see boot.ci. plot a logical variable, indicating whether a plot of the single bootstrap density should

Details

Frei and Wunsch (2018) introduced an estimator which simultaneously corrects the bias of a short default time series and an bias due to autocorrelation. Additionally, further corrections are implemented. If DB is specified, the single bootstrap corrected estimate will be calculated by using the bootstrap values of the outer loop (oValues).

Value

The returned value is a list, containing the following components (depending on the selected arguments):

Original Estimate of the original method
Bootstrap Bootstrap corrected estimate

be generated.

Double_Bootstrap

Double bootstrap corrected estimate

Jackknife Jackknife corrected estimate

CI_Boot Selected two-sided bootstrap confidence interval bValues Estimates from the single bootstrap resampling

iValues Estimates from the double bootstrap resampling- inner loop oValues Estimates from the double bootstrap resampling- outer loop

References

Chang J, Hall P (2015). "Double-bootstrap methods that use a single double-bootstrap simulation." *Biometrika*, **102**(1), 203–214.

Efron B, Tibshirani RJ (1994). An introduction to the bootstrap. CRC press.

Frei C, Wunsch M (2018). "Moment Estimators for Autocorrelated Time Series and their Application to Default Correlations." *Journal of Credit Risk*, **14**, 1–29.

intraFMM 35

See Also

intraAMM, intraFMM, intraJDP2, intraMLE, intraJDP1, intraAMLE, intraMode,intraBeta

Examples

```
set.seed(10)
d=defaultTimeseries(1000,0.1,10,0.01)
n=rep(1000,10)

IntraCorr=intraCMM(d,n,l=0)

#Estimation with two lags of autocorrelation
IntraCorr=intraCMM(d,n, l=2 )

#Jackknife correction
IntraCorr=intraCMM(d,n, JC=TRUE)

#Bootstrap correction with bootstrap confidence intervals
IntraCorr=intraCMM(d,n, B=1000, CI_Boot=0.95 )

#Bootstrap correction with bootstrap confidence intervals and plot
IntraCorr=intraCMM(d,n, B=1000, CI_Boot=0.95, plot=TRUE )

#Double Bootstrap correction with 10 repetitions in the inner loop and 50 in the outer loop
IntraCorr=intraCMM(d,n, DB=c(10,50))
```

intraFMM

Finite Sample Method of Moments Estimator

Description

The intra asset correlation will be estimated by fitting the first two moments of the default rate time series to the theoretical moments of the default rate and backing out the remaining correlation parameter numerically. The sample variance will be adjusted for an insufficiently large portfolio size. Additionally, bootstrap and jackknife corrections are implemented.

Usage

```
intraFMM(d, n, B = 0, DB=c(0,0), JC = FALSE, CI_Boot, type="bca", plot=FALSE)
```

36 intraFMM

Arguments

d	a vector, containing the default time series of the sector.
n	a vector, containing the number of obligors at the beginning of the period over time.
В	an integer, indicating how many bootstrap repetitions should be used for the single bootstrap corrected estimate.
DB	a combined vector, indicating how many bootstrap repetitions should be used for the inner (first entry) and outer loop (second entry) to correct the bias using the double bootstrap.
JC	a logical variable, indicating if the jackknife corrected estimate should be calculated.
CI_Boot	a number, indicating the desired confidence interval if the single bootstrap correction is specified. By default, the interval is calculated as the bootstrap corrected and accelerated confidence interval (Bca).
type	a string, indicating the desired method to calculate the bootstrap confidence intervals. For more details see boot.ci. Studendized confidence intervals are not supported.
plot	a logical variable, indicating whether a plot of the single bootstrap density should be generated.

Details

As stated by Vasicek (1991) and Vasicek (2002), the asset variables follow a bivariate normal distribution. Since this distribution can be parametrized by the first two moments, namely the expected value and the variance, the remaining correlation parameter can be backed out numerically. The expected value will be approximated by the mean of the default rate and the variance is defined as the (corrected) sample variance of the default rate. For theoretical background, see Gordy (2000). If DB is specified, the single bootstrap corrected estimate will be calculated by using the bootstrap values of the outer loop (oValues).

Value

The returned value is a list, containing the following components (depending on the selected arguments):

Original Estimate of the original method
Bootstrap Bootstrap corrected estimate

Double_Bootstrap

Double bootstrap corrected estimate

Jackknife Jackknife corrected estimate

CI_Boot Selected two-sided bootstrap confidence interval

bValues Estimates from the bootstrap resampling

iValues Estimates from the double bootstrap resampling- inner loop oValues Estimates from the double bootstrap resampling- outer loop

intraJDP1 37

References

Chang J, Hall P (2015). "Double-bootstrap methods that use a single double-bootstrap simulation." *Biometrika*, **102**(1), 203–214.

Efron B, Tibshirani RJ (1994). An introduction to the bootstrap. CRC press.

Gordy MB (2000). "A comparative anatomy of credit risk models." *Journal of Banking & Finance*, **24**(1), 119–149.

Vasicek O (1991). "Limiting loan loss probability distribution." *Finance, Economics and Mathematics*, 147–148.

Vasicek O (2002). "The distribution of loan portfolio value." *Risk*, **15**(12), 160–162.

See Also

intraAMM, intraJDP1, intraJDP2, intraCMM, intraMLE, intraAMLE, intraMode, intraBeta

Examples

```
set.seed(111)
d=defaultTimeseries(1000,0.3,20,0.01)
n=rep(1000,20)

IntraCorr=intraFMM(d,n)

#Jackknife correction
IntraCorr=intraFMM(d,n, JC=TRUE)

#Bootstrap correction with confidence intervals
IntraCorr=intraFMM(d,n, B=1000, CI_Boot=0.95 )

#Bootstrap correction with confidence intervals and plot
IntraCorr=intraFMM(d,n, B=1000, CI_Boot=0.95, plot=TRUE )

#Double Bootstrap correction with 10 repetitions in the inner loop and 50 in the outer loop
IntraCorr=intraFMM(D1,N1, DB=c(10,50))
```

intraJDP1

Joint Default Probability Matching Estimator, Lucas (1995)

Description

The intra asset correlation will be estimated by fitting the empirical joint default probability (JDP) of the default rate time series to the theoretical one and backing out the remaining correlation parameter numerically. The unbiased estimator of Lucas (1995) will be used for the empirical JDP. Additionally, bootstrap and jackknife corrections are implemented.

38 intraJDP1

Usage

```
intraJDP1(d, n, B = 0, DB=c(0,0), JC = FALSE, CI_Boot, type="bca", plot=FALSE)
```

Arguments

d	a vector, containing the default time series of the sector.
n	a vector, containing the number of obligors at the beginning of the period over time.
В	an integer, indicating how many bootstrap repetitions should be used for the single bootstrap corrected estimate.
DB	a combined vector, indicating how many bootstrap repetitions should be used for the inner (first entry) and outer loop (second entry) to correct the bias using the double bootstrap.
JC	a logical variable, indicating if the jackknife corrected estimate should be calculated.
CI_Boot	a number, indicating the desired confidence interval if the single bootstrap correction is specified. By default, the interval is calculated as the bootstrap corrected and accelerated confidence interval (Bca).
type	a string, indicating the desired method to calculate the bootstrap confidence intervals. For more details see boot.ci. Studendized confidence intervals are not supported.
plot	a logical variable, indicating whether a plot of the single bootstrap density should be generated.

Details

Kalkbrener and Onwunta (2010) for example showed that the JDP of the default rates follow a bivariate normal distribution. The intra asset correlation will be estimated by fitting the empirical JDP of the default rate time series on the theoretical JDP of the default rate and backing out the remaining correlation parameter numerically. The empirical JDP is calculated by the (unbiased) estimator of Lucas (1995). If DB is specified, the single bootstrap corrected estimate will be calculated by using the bootstrap values of the outer loop (oValues).

Value

The returned value is a list, containing the following components (depending on the selected arguments):

Original Estimate of the original method Bootstrap Corrected estimate

Double_Bootstrap

Double bootstrap corrected estimate

Jackknife Jackknife corrected estimate

CI_Boot Selected two-sided bootstrap confidence interval

bValues Estimates from the bootstrap resampling

iValues Estimates from the double bootstrap resampling- inner loop oValues Estimates from the double bootstrap resampling- outer loop

intraJDP2 39

References

Chang J, Hall P (2015). "Double-bootstrap methods that use a single double-bootstrap simulation." *Biometrika*, **102**(1), 203–214.

Efron B, Tibshirani RJ (1994). An introduction to the bootstrap. CRC press.

Kalkbrener M, Onwunta A (2010). "Validating structural credit portfolio models." *Model risk - identification, measurement and management. Risk Books, London*, 233–261.

Lucas DJ (1995). "Default correlation and credit analysis." *The Journal of Fixed Income*, **4**(4), 76–87.

See Also

intraAMM, intraFMM, intraJDP2, intraCMM, intraMLE, intraAMLE, intraMode,intraBeta

Examples

```
set.seed(111)
d=defaultTimeseries(1000,0.3,20,0.01)
n=rep(1000,20)

IntraCorr=intraJDP1(d,n)
#Jackknife correction
IntraCorr=intraJDP1(d,n, JC=TRUE)

#Bootstrap correction with confidence intervals
IntraCorr=intraJDP1(d,n, B=1000, CI_Boot=0.95)

#Bootstrap correction with confidence intervals and plot
IntraCorr=intraJDP1(d,n, B=1000, CI_Boot=0.95, plot=TRUE)

#Double Bootstrap correction with 10 repetitions in the inner loop and 50 in the outer loop
IntraCorr=intraJDP1(D1,N1, DB=c(10,50))
```

intraJDP2

Joint Default Probability Matching Estimator, De Servigny and Renault (2002)

Description

The intra asset correlation will be estimated by fitting the empirical joint default probability (JDP) of the default rate time series to the theoretical one and backing out the remaining correlation parameter numerically. The biased estimator of De Servigny and Renault (2002) will be used for the empirical JDP. Additionally, bootstrap and jackknife corrections are implemented.

40 intraJDP2

Usage

```
intraJDP2(d, n, B = 0,DB=c(0,0), JC = FALSE, CI_Boot, type="bca", plot=FALSE)
```

Arguments

d	a vector, containing the default time series of the sector.
n	a vector, containing the number of obligors at the beginning of the period over time.
В	an integer, indicating how many bootstrap repetitions should be used for the single bootstrap corrected estimate.
DB	a combined vector, indicating how many bootstrap repetitions should be used for the inner (first entry) and outer loop (second entry) to correct the bias using the double bootstrap.
JC	a logical variable, indicating if the jackknife corrected estimate should be calculated.
CI_Boot	a number, indicating the desired confidence interval if the single bootstrap correction is specified. By default, the interval is calculated as the bootstrap corrected and accelerated confidence interval (Bca).
type	a string, indicating the desired method to calculate the bootstrap confidence intervals. For more details see boot.ci. Studendized confidence intervals are not supported.
plot	a logical variable, indicating whether a plot of the single bootstrap density should be generated.

Details

Kalkbrener and Onwunta (2010) for example showed that the JDP of the default rates follow a bivariate normal distribution. The intra asset correlation will be estimated by fitting the empirical JDP of the default rate time series on the theoretical JDP of the default rate and backing out the remaining correlation parameter numerically. The empirical JDP is calculated by the (unbiased) estimator of De Servigny and Renault (2002). If DB is specified, the single bootstrap corrected estimate will be calculated by using the bootstrap values of the outer loop (oValues).

Value

The returned value is a list, containing the following components (depending on the selected arguments):

Original Estimate of the original method
Bootstrap Bootstrap corrected estimate

Double_Bootstrap

Double bootstrap corrected estimate

Jackknife Jackknife corrected estimate

CI_Boot Selected two-sided bootstrap confidence interval bValues Estimates from the single bootstrap resampling

iValues Estimates from the double bootstrap resampling- inner loop oValues Estimates from the double bootstrap resampling- outer loop

References

Chang J, Hall P (2015). "Double-bootstrap methods that use a single double-bootstrap simulation." *Biometrika*, **102**(1), 203–214.

De Servigny A, Renault O (2002). "Default correlation: empirical evidence." *Working Paper, Standard and Poors*. Available at: https://www.semanticscholar.org/paper/Default-correlation% 3A-empirical-evidence-Servigny-Renault/aae251436d0e3b489951c0d38463d71106755675.

Efron B, Tibshirani RJ (1994). An introduction to the bootstrap. CRC press.

Kalkbrener M, Onwunta A (2010). "Validating structural credit portfolio models." *Model risk - identification, measurement and management. Risk Books, London*, 233–261.

See Also

```
intraAMM, intraFMM, intraJDP1, intraCMM, intraMLE, intraAMLE, intraMode,intraBeta
```

Examples

```
set.seed(10)
d=defaultTimeseries(1000,0.3,20,0.01)
n=rep(1000,20)

IntraCorr=intraJDP2(d,n)
#Jackknife correction
IntraCorr=intraJDP2(d,n, JC=TRUE)

#Bootstrap correction with confidence intervals
IntraCorr=intraJDP2(d,n, B=1000, CI_Boot=0.95)

#Bootstrap correction with confidence intervals and plot
IntraCorr=intraJDP2(d,n, B=1000, CI_Boot=0.95, plot=TRUE)

#Double Bootstrap correction with 10 repetitions in the inner loop and 50 in the outer loop
IntraCorr=intraJDP2(D1,N1, DB=c(10,50))
```

intraMLE

Binomial Maximum Likelihood Estimator

Description

The default process in the Vasicek model follows a binomial distribution, conditional on the realization of the systematic factor. Hence, the intra asset correlation can be estimated by maximizing the Vasicek-binomial log likelihood.

Usage

```
intraMLE(d, n, B =0, DB=c(0,0), JC = FALSE, CI, CI_Boot, type="bca", plot=FALSE)
```

Arguments

d	a vector, containing the default time series of the sector.
n	a vector, containing the number of obligors at the beginning of the period in the sector.
В	an integer, indicating how many bootstrap repetitions should be used for the single bootstrap corrected estimate.
DB	a combined vector, indicating how many bootstrap repetitions should be used for the inner (first entry) and outer loop (second entry) to correct the bias using the double bootstrap.
JC	a logical variable, indicating if the jackknife corrected estimate should be calculated.
CI	a number, indicating the desired asymptotic confidence interval of the estimate.
CI_Boot	a number, indicating the desired bootstrap confidence interval of the estimate, if the single bootstrap correction is specified. By default, the interval is calculated as the bootstrap corrected and accelerated confidence interval (Bca). Furthermore, the analytical confidence intervals are provided, using the same value as CI_Boot.
type	a string, indicating the type of bootstrap intervals. For more details see boot.ci.
plot	a logical variable, indicating whether a plot of the single bootstrap density should be generated.

Details

In the Vasicek model the default process can be expressed as independent binomial trials, conditional on the realization of the systematic factor. Therefore Gordy and Heitfield (2010) introduced an estimator of the intra asset correlation based on the log-likelihood maximization. For theoretical background see Gordy and Heitfield (2010).

The log-likelihood will be maximized for values between 0 and 1. The asymptotic confidence interval will be estimated using maximum likelihood theory. If DB is specified, the single bootstrap corrected estimate will be calculated by using the bootstrap values of the outer loop (oValues).

Value

The returned value is a list, containing the following components (depending on the selected arguments):

Original Estimate of the original method
Bootstrap Bootstrap corrected estimate
Double_Bootstrap

Double bootstrap corrected estimate

Jackknife Jackknife corrected estimate

CI Selected two-sided asymptotic confidence interval CI_Boot Selected two-sided bootstrap confidence interval bValues Estimates from the single bootstrap resampling

iValues Estimates from the double bootstrap resampling- inner loop oValues Estimates from the double bootstrap resampling- outer loop

intraMode 43

References

Chang J, Hall P (2015). "Double-bootstrap methods that use a single double-bootstrap simulation." *Biometrika*, **102**(1), 203–214.

Efron B, Tibshirani RJ (1994). An introduction to the bootstrap. CRC press.

Gordy MB, Heitfield E (2010). "Small-sample estimation of models of portfolio credit risk." In Recent Advances in Financial Engineering: Proceedings of the KIER-TMU International Workshop on Financial Engineering, 2009: Otemachi, Sankei Plaza, Tokyo, 3-4 August 2009, 43–63.

See Also

intraAMM, intraFMM, intraJDP2, intraCMM, intraJDP1, intraAMLE, intraMode,intraBeta

Examples

```
set.seed(11)
d=defaultTimeseries(1000,0.3,20,0.01)
n=rep(1000,20)

IntraCorr=intraMLE(d,n)

#Estimation with confidence intervals
IntraCorr=intraMLE(d,n, CI=0.95 )

#Jackknife correction
IntraCorr=intraMLE(d,n, JC=TRUE)

#Bootstrap correction with bootstrap confidence intervals
IntraCorr=intraMLE(d,n, B=1000, CI_Boot=0.95 )

#Bootstrap correction with bootstrap confidence intervals and plot
IntraCorr=intraMLE(d,n, B=1000, CI_Boot=0.95, plot=TRUE )

#Double Bootstrap correction with 10 repetitions in the inner loop and 50 in the outer loop
IntraCorr=intraMLE(D1,N1, DB=c(10,50))
```

44 intraMode

Description

The intra asset correlation will be estimated by fitting the mode of the default rate time series to the theoretical mode of the default rates and backing out the remaining correlation parameter numerically. Additionally, bootstrap and jackknife corrections are implemented.

Usage

```
intraMode(d, n, B = 0, DB=c(0,0), JC = FALSE,CI_Boot, type="bca", plot=FALSE)
```

Arguments

d	a vector, containing the default time series of the sector.
n	a vector, containing the number of obligors at the beginning of the period over time.
В	an integer, indicating how many bootstrap repetitions should be used for the single bootstrap corrected estimate.
DB	a combined vector, indicating how many bootstrap repetitions should be used for the inner (first entry) and outer loop (second entry) to correct the bias using the double bootstrap.
JC	a logical variable, indicating if the jackknife corrected estimate should be calculated.
CI_Boot	a number, indicating the desired confidence interval if the single bootstrap correction is specified. By default, the interval is calculated as the bootstrap corrected and accelerated confidence interval (Bca).
type	a string, indicating the desired method to calculate the bootstrap confidence intervals. For more details see boot.ci. Studendized confidence intervals are not supported.
plot	a logical variable, indicating whether a plot of the single bootstrap density should be generated.

Details

As stated by Botha and van Vuuren (2010) one can estimate the intra correlation by matching the theoretical and empirical mode. According to Vasicek (1991) the default rates are only unimodal if the intra correlation is smaller than 0.5. Therefore, this estimator cannot be used for higher intra correlations. The theoretical mode is given by Vasicek (1991):

$$Mode_Vasicek = Phi(sqrt(1 - rho)/(1 - 2 * rho) * Phi^-1(PD))$$

If DB is specified, the single bootstrap corrected estimate will be calculated by using the bootstrap values of the outer loop (oValues).

Value

The returned value is a list, containing the following components (depending on the selected arguments):

intraMode 45

Original Estimate of the original method
Bootstrap Bootstrap corrected estimate

Double_Bootstrap

Double bootstrap corrected estimate

Jackknife Jackknife corrected estimate

CI_Boot Selected two-sided bootstrap confidence interval

bValues Estimates from the bootstrap resampling

iValues Estimates from the double bootstrap resampling- inner loop oValues Estimates from the double bootstrap resampling- outer loop

References

Botha M, van Vuuren G (2010). "Implied asset correlation in retail loan portfolios." *Journal of Risk Management in Financial Institutions*, **3**(2), 156–173.

Chang J, Hall P (2015). "Double-bootstrap methods that use a single double-bootstrap simulation." *Biometrika*, **102**(1), 203–214.

Efron B, Tibshirani RJ (1994). An introduction to the bootstrap. CRC press.

Gordy MB (2000). "A comparative anatomy of credit risk models." *Journal of Banking & Finance*, **24**(1), 119–149.

Vasicek O (1991). "Limiting loan loss probability distribution." *Finance, Economics and Mathematics*, 147–148.

See Also

intraFMM, intraJDP1, intraJDP2 intraCMM, intraMLE, intraAMLE, intraBeta

Examples

```
set.seed(111)
d=defaultTimeseries(1000,0.3,20,0.01)
n=rep(1000,20)

IntraCorr=intraMode(d,n)

#Jackknife correction
IntraCorr=intraMode(d,n, JC=TRUE)

#Bootstrap correction with confidence intervals
IntraCorr=intraMode(d,n, B=1000, CI_Boot=0.95)

#Bootstrap correction with confidence intervals and plot
IntraCorr=intraMode(d,n, B=1000, CI_Boot=0.95, plot=TRUE)

#Double Bootstrap correction with 10 repetitions in the inner loop and 50 in the outer loop
IntraCorr=intraMode(D1,N1, DB=c(10,50))
```

Index

* ALL	boot.ci, 5, 9, 12, 14, 17, 19, 23, 27, 29, 31,
<pre>analyze_AssetCorr, 5</pre>	34, 36, 38, 40, 42, 44
interALL, 9	
intraALL, 23	defaultTimeseries, 8
* AMLE	
intraAMLE, 25	interALL, 7, 9
* AMM	interCMM, 7, 11, 15, 18, 20, 22
intraAMM,29	interCopula, 7, 13, 14, 18, 20, 22
* Beta	interCov, 7, 13, 15, 16, 20, 22
intraBeta, 31	interJDP, 7, 13, 15, 18, 18, 22
* CMM	interMLE, 7, 13, 15, 18, 20, 21
intraCMM, 33	intraALL, 7, 23
* Copula	intraAMLE, 25, 30, 33, 35, 37, 39, 41, 43, 45
interCopula, 14	intraAMM, 7, 11, 25, 28, 29, 35, 37, 39, 41, 43
* FMM	intraBeta, 7, 25, 28, 30, 31, 35, 37, 39, 41,
intraFMM, 35	43, 45
* JDP1	intraCMM, 7, 11, 25, 28, 30, 33, 33, 37, 39, 41,
intraJDP1, 37	43, 45
* JDP2	intraFMM, 7, 11, 25, 28, 30, 33, 35, 35, 39, 41,
intraJDP2, 39	43, 45
* MLE	intraJDP1, 7, 11, 25, 28, 30, 33, 35, 37, 37,
intraMLE, 41	41, 43, 45
* Mode	intraJDP2, 7, 11, 25, 28, 30, 33, 35, 37, 39,
intraMode, 43	39, 43, 45
* defaultimeseries	intraMLE, 7, 11, 25, 28, 30, 33, 35, 37, 39, 41,
defaultTimeseries, 8	41, 45
* interCMM	intraMode, 7, 25, 28, 30, 33, 35, 37, 39, 41,
interCMM, 11	<i>43</i> , 43
* interCov	
interCov, 16	
* interJDP	
interJDP, 18	
* interJPD	
interJDP, 18	
* interMLE	
interMLE, 21	
2110011122, 21	
analyze_AssetCorr, 5	
AssetCorr (AssetCorr-package), 2	
AssetCorr-package, 2	