

# Package ‘tm1r’

October 14, 2022

**Type** Package

**Title** The Integration Between 'IBM COGNOS TM1' and R

**Version** 1.1.8

**Author** Muhammed Ali Onder

**Maintainer** Muhammed Ali Onder <muhammedalionder@gmail.com>

**Description** Useful functions to connect to 'TM1' <<https://www.ibm.com/uk-en/products/planning-and-analytics>> instance from R via REST API. With the functions in the package, data can be imported from 'TM1' via mdx view or native view, data can be sent to 'TM1', processes and chores can be executed, and cube and dimension metadata information can be taken.

**License** GPL (>= 2)

**Encoding** UTF-8

**LazyData** true

**Imports** jsonlite, httr

**Depends** R (>= 3.0.0)

**NeedsCompilation** no

**URL** <https://github.com/muhammedalionder/tm1r>

**BugReports** <https://github.com/muhammedalionder/tm1r/issues>

**Repository** CRAN

**Date/Publication** 2020-12-09 20:40:02 UTC

## R topics documented:

tm1_api_request . . . . .	2
tm1_connection . . . . .	3
tm1_create_element . . . . .	4
tm1_create_mdx . . . . .	4
tm1_create_subset . . . . .	7
tm1_create_view . . . . .	7
tm1_delete_element . . . . .	8

tm1_delete_subset . . . . .	9
tm1_delete_view . . . . .	10
tm1_get_config . . . . .	10
tm1_get_cubes . . . . .	11
tm1_get_cube_dimensions . . . . .	11
tm1_get_data . . . . .	12
tm1_get_dimensions . . . . .	13
tm1_get_dimension_attributes . . . . .	14
tm1_get_dimension_elements . . . . .	14
tm1_get_dimension_subsets . . . . .	15
tm1_get_element . . . . .	16
tm1_get_instances . . . . .	16
tm1_get_log . . . . .	17
tm1_get_mdx_view . . . . .	17
tm1_get_native_view . . . . .	18
tm1_get_subset_elements . . . . .	19
tm1_logout . . . . .	20
tm1_run_chore . . . . .	20
tm1_run_process . . . . .	21
tm1_send_data . . . . .	22
tm1_send_dataset . . . . .	23

<b>Index</b>	<b>25</b>
--------------	-----------

---

tm1_api_request	<i>TM1 API Request</i>
-----------------	------------------------

---

## Description

Makes a api request to tm1 server with url and body specified

## Usage

```
tm1_api_request(tm1_connection, url, body = "", type = "GET")
```

## Arguments

tm1_connection	tm1 connection object returned by the function tm1_connection
url	URL address for rest api request
body	body text of request
type	type of api request. Requests in httr package are supported like GET, POST, DELETE, PATCH

**Examples**

```
## Not run:
con_obj <- tm1_connection("localhost", "8881", "admin", "apple")
url <- "https://localhost:8881/api/v1/Cubes('SalesCube')/Dimensions"
tm1_api_request(con_obj, url, type = "GET")

## End(Not run)
```

---

tm1_connection	<i>TM1 Connection</i>
----------------	-----------------------

---

**Description**

Creates and returns a connection object to connect to TM1 via REST API.

**Usage**

```
tm1_connection(adminhost = "localhost", httpport = "",
username = "admin", password = "apple",
namespace="", ssl=TRUE, base_url="")
```

**Arguments**

adminhost	adminhost of tm1 model
httpport	httpport of tm1 model
username	username to connect to tm1 model
password	password of the username
namespace	ID of namespace should be specified if there is CAM security. Should be blank for native security
ssl	If UseSSL parameter is T in tm1s.cfg file, then TRUE. Else FALSE. Default is TRUE
base_url	when connecting to cloud, this option can be used instead of adminhost and httpport

**Examples**

```
## Not run:
tm1_connection("localhost", "8881", "admin", "apple")
tm1_connection(username="admin", password="apple",
base_url = "https://[Customer_Name].planning-analytics.ibmcloud.com/tm1/api/[Server Name]/")

## End(Not run)
```

---

tm1_create_element	<i>TM1 Create New Element to a Dimension</i>
--------------------	--

---

### Description

Inserts a new element to the dimension

### Usage

```
tm1_create_element(tm1_connection,
  dimension, element, parent="", weight=1, type="Numeric")
```

### Arguments

tm1_connection	tm1 connection object returned by the function tm1_connection
dimension	Name of dimension
element	Name of new element
parent	Name of parent of new element. Leave blank if there is no parent.
weight	Weight of the element as a component to the parent. Default is 1
type	type of element; Numeric, String or Consolidated. Default is Numeric

### Examples

```
## Not run:
tm1_create_element(tm1_connection("localhost", "8881", "admin", "apple"),
  "month", "test", "Year")

con_obj <- tm1_connection("localhost", "8881", "admin", "apple")
tm1_create_element(con_obj, "month", "test", "Year")

## End(Not run)
```

---

tm1_create_mdx	<i>TM1 Generate mdx for a cube view</i>
----------------	---

---

### Description

Returns mdx as a string to use in the function tm1\_get\_mdx\_view

**Usage**

```
tm1_create_mdx(cube,
               rowdim1, rowsub1, rowel1,
               rowdim2, rowsub2, rowel2,
               rowdim3, rowsub3, rowel3,
               coldim1, colsub1, colel1,
               coldim2, colsub2, colel2,
               titledim1, titleel1,
               titledim2, titleel2,
               titledim3, titleel3,
               titledim4, titleel4,
               titledim5, titleel5,
               titledim6, titleel6,
               titledim7, titleel7,
               titledim8, titleel8,
               titledim9, titleel9,
               titledim10, titleel10,
               rowsuppress, colsuppress )
```

**Arguments**

cube	Name of the cube
rowdim1	Name of dimension in 1st row
rowsub1	Subset of dimension in 1st row
rowel1	Element of dimension in 1st row. If multiple, seperated by " ". This should be passed if subset is not provided
rowdim2	Name of dimension in 2nd row
rowsub2	Subset of dimension in 2nd row
rowel2	Element of dimension in 2nd row. If multiple, seperated by " ". This should be passed if subset is not provided
rowdim3	Name of dimension in 3rd row
rowsub3	Subset of dimension in 3rd row
rowel3	Element of dimension in 3rd row. If multiple, seperated by " ". This should be passed if subset is not provided
coldim1	Name of dimension in 1st col
colsub1	Subset of dimension in 1st col
colel1	Element of dimension in 1st col. If multiple, seperated by " ". This should be passed if subset is not provided
coldim2	Name of dimension in 2nd col
colsub2	Subset of dimension in 2nd col
colel2	Element of dimension in 2nd col. If multiple, seperated by " ". This should be passed if subset is not provided
titledim1	Name of dimension in title

titleel1	Element of dimension in corresponding titledim
titledim2	Name of dimension in title
titleel2	Element of dimension in corresponding titledim
titledim3	Name of dimension in title
titleel3	Element of dimension in corresponding titledim
titledim4	Name of dimension in title
titleel4	Element of dimension in corresponding titledim
titledim5	Name of dimension in title
titleel5	Element of dimension in corresponding titledim
titledim6	Name of dimension in title
titleel6	Element of dimension in corresponding titledim
titledim7	Name of dimension in title
titleel7	Element of dimension in corresponding titledim
titledim8	Name of dimension in title
titleel8	Element of dimension in corresponding titledim
titledim9	Name of dimension in title
titleel9	Element of dimension in corresponding titledim
titledim10	Name of dimension in title
titleel10	Element of dimension in corresponding titledim
rowsuppress	TRUE if zeroes are suppressed on rows
colsuppress	TRUE if zeroes are suppressed on columns

### Examples

```
## Not run:
```

```
tm1_create_mdx( "SalesCube", rowdim1="account1", rowel1 = "Sales", coldim1="month", colel1="Jan",
  titledim1 = "actvsbud", titleel1 = "Actual",
  titledim2 = "region", titleel2 = "Argentina",
  titledim3 = "model", titleel3 = "S Series 1.8 L Sedan",
  rowsuppress=TRUE, colsuppress = FALSE)
```

```
## End(Not run)
```

---

tm1_create_subset	<i>TM1 Create New Subset to a Dimension</i>
-------------------	---

---

**Description**

Creates a new subset to the dimension

**Usage**

```
tm1_create_subset(tm1_connection,  
  dimension, subset, element="", mdx="", overwrite=TRUE)
```

**Arguments**

tm1_connection	tm1 connection object returned by the function tm1_connection
dimension	Name of dimension
subset	Name of new subset
element	Name of elements separated by   for static subset
mdx	mdx of subset for dynamic subset
overwrite	TRUE or FALSE. If TRUE, subset is overwritten

**Examples**

```
## Not run:  
tm1_create_subset(tm1_connection("localhost", "8881", "admin", "apple"),  
  "month", "Q1Months", element = "Jan|Feb|Mar")  
  
con_obj <- tm1_connection("localhost", "8881", "admin", "apple")  
tm1_create_element(con_obj, "month", "all", mdx = "[month].MEMBERS")  
  
## End(Not run)
```

---

tm1_create_view	<i>TM1 Create View from mdx</i>
-----------------	---------------------------------

---

**Description**

Creates cube view with mdx

**Usage**

```
tm1_create_view(tm1_connection, cube, view, mdx)
```

**Arguments**

tm1_connection	tm1 connection object returned by the function tm1_connection
cube	Name of cube
view	Name of view to be created
mdx	MDX of view as a string

**Examples**

```
## Not run:
mdx <- "SELECT
  NON EMPTY
    {[month].[Jan],[month].[Feb],[month].[Mar]}
  ON COLUMNS,
  NON EMPTY
    {[account1].[Price],[account1].[Units]}
  ON ROWS
FROM [SalesCube]
WHERE
  (
    [actvsbud].[actvsbud].[Actual],
    [region].[region].[Argentina],
    [model].[model].[S Series 1.8 L Sedan]
  )"
tm1_create_view(
  tm1_connection("localhost", "8881", "admin", "apple"),
  "SalesCube", "test", mdx)

con_obj <- tm1_connection("localhost", "8881", "admin", "apple")
tm1_create_view(con_obj, "SalesCube", "test", mdx)

## End(Not run)
```

---

tm1_delete_element	<i>TM1 Delete Element or Component</i>
--------------------	--

---

**Description**

Deletes element or component from dimensions

**Usage**

```
tm1_delete_element(tm1_connection,
  dimension, element, parent="")
```



**Arguments**

tm1_connection	tm1 connection object returned by the function tm1_connection
dimension	Name of dimension
element	Name of element
parent	Name of parent of element. If parent is specified, component delete will be done. If parent is omitted, element will be deleted from dimension

**Examples**

```
## Not run:
tm1_delete_element(tm1_connection("localhost", "8881", "admin", "apple"),
"month", "test", "Year")

con_obj <- tm1_connection("localhost", "8881", "admin", "apple")
tm1_delete_element(con_obj, "month", "test")

## End(Not run)
```

---

tm1_delete_subset	<i>TM1 Delete Subset</i>
-------------------	--------------------------

---

**Description**

Deletes subset from dimensions

**Usage**

```
tm1_delete_subset(tm1_connection,
dimension, subset)
```

**Arguments**

tm1_connection	tm1 connection object returned by the function tm1_connection
dimension	Name of dimension
subset	Name of subset

**Examples**

```
## Not run:
tm1_delete_subset(tm1_connection("localhost", "8881", "admin", "apple"),
"month", "test")

con_obj <- tm1_connection("localhost", "8881", "admin", "apple")
tm1_delete_subset(con_obj, "month", "test")

## End(Not run)
```

---

tm1_delete_view	<i>TM1 Delete View</i>
-----------------	------------------------

---

**Description**

Deletes cube view

**Usage**

```
tm1_delete_view(tm1_connection, cube, view)
```

**Arguments**

tm1_connection	tm1 connection object returned by the function tm1_connection
cube	Name of cube
view	Name of view to be deleted

**Examples**

```
## Not run:  
  
tm1_delete_view(  
  tm1_connection("localhost", "8881", "admin", "apple"),  
  "SalesCube", "test")  
  
con_obj <- tm1_connection("localhost", "8881", "admin", "apple")  
tm1_delete_view(con_obj, "SalesCube", "test")  
  
## End(Not run)
```

---

tm1_get_config	<i>TM1 Get Configuration</i>
----------------	------------------------------

---

**Description**

Gets configuration of tm1 instance

**Usage**

```
tm1_get_config(tm1_connection)
```

**Arguments**

tm1_connection	tm1 connection object returned by the function tm1_connection
----------------	---

**Examples**

```
## Not run:
tm1_get_config(tm1_connection("localhost", "8881", "admin", "apple"))

con_obj <- tm1_connection("localhost", "8881", "admin", "apple")
tm1_get_config(con_obj)

## End(Not run)
```

---

tm1_get_cubes	<i>TM1 Get Cubes</i>
---------------	----------------------

---

**Description**

Gets list of cubes

**Usage**

```
tm1_get_cubes(tm1_connection, ShowControlObjects = FALSE)
```

**Arguments**

**tm1\_connection** tm1 connection object returned by the function `tm1_connection`  
**ShowControlObjects**  
If TRUE, control cubes are also listed. Default is FALSE

**Examples**

```
## Not run:
tm1_get_cubes(tm1_connection("localhost", "8881", "admin", "apple"))

con_obj <- tm1_connection("localhost", "8881", "admin", "apple")
tm1_get_cubes(con_obj)

## End(Not run)
```

---

tm1_get_cube_dimensions	<i>TM1 Get Dimensions of a Cube</i>
-------------------------	-------------------------------------

---

**Description**

Gets dimensions of a cube

**Usage**

```
tm1_get_cube_dimensions(tm1_connection, cube)
```

**Arguments**

tm1\_connection tm1 connection object returned by the function tm1\_connection  
 cube Name of a cube as a string

**Examples**

```
## Not run:
tm1_get_cube_dimensions(
tm1_connection("localhost", "8881", "admin", "apple"),
"SalesCube")

con_obj <- tm1_connection("localhost", "8881", "admin", "apple")
tm1_get_cube_dimensions(con_obj, "SalesCube")

## End(Not run)
```

---

tm1_get_data	<i>TM1 Get Data from a Cube</i>
--------------	---------------------------------

---

**Description**

Gets data from a cube, Supports up-to 10 dimension for now

**Usage**

```
tm1_get_data(tm1_connection, cube,
             element1="", element2="",
             element3="", element4="",
             element5="", element6="",
             element7="", element8="",
             element9="", element10="")
```

**Arguments**

tm1\_connection tm1 connection object returned by the function tm1\_connection  
 cube Name of a cube as a string  
 element1 Element from 1st dimension of cube. Leave empty if there is no corresponding dimension  
 element2 Element from 2nd dimension of cube. Leave empty if there is no corresponding dimension  
 element3 Element from 3rd dimension of cube. Leave empty if there is no corresponding dimension  
 element4 Element from 4th dimension of cube. Leave empty if there is no corresponding dimension  
 element5 Element from 5th dimension of cube. Leave empty if there is no corresponding dimension

element6	Element from 6th dimension of cube. Leave empty if there is no corresponding dimension
element7	Element from 7th dimension of cube. Leave empty if there is no corresponding dimension
element8	Element from 8th dimension of cube. Leave empty if there is no corresponding dimension
element9	Element from 9th dimension of cube. Leave empty if there is no corresponding dimension
element10	Element from 10th dimension of cube. Leave empty if there is no corresponding dimension

### Examples

```
## Not run:
tm1_get_data(
  tm1_connection("localhost", "8881", "admin", "apple"),
  "SalesCube", "Actual", "Argentina", "Total", "Sales", "Jan")

con_obj <- tm1_connection("localhost", "8881", "admin", "apple")
tm1_get_data(con_obj, "SalesCube", "Actual", "Argentina", "Total", "Sales", "Jan")

## End(Not run)
```

---

tm1_get_dimensions	<i>TM1 Get Dimensions</i>
--------------------	---------------------------

---

### Description

Gets list of dimensions

### Usage

```
tm1_get_dimensions(tm1_connection, ShowControlObjects = FALSE)
```

### Arguments

**tm1\_connection** tm1 connection object returned by the function `tm1_connection`  
**ShowControlObjects**  
 If TRUE, control dimensions are also listed. Default is FALSE

### Examples

```
## Not run:
tm1_get_dimensions(tm1_connection("localhost", "8881", "admin", "apple"))

con_obj <- tm1_connection("localhost", "8881", "admin", "apple")
tm1_get_dimensions(con_obj)

## End(Not run)
```

tm1\_get\_dimension\_attributes

*TM1 Get Attributes of a Dimension*

---

### **Description**

Gets attributes of a dimension

### **Usage**

```
tm1_get_dimension_attributes(tm1_connection, dimension)
```

### **Arguments**

tm1\_connection tm1 connection object returned by the function tm1\_connection  
dimension Name of a dimension as a string

### **Examples**

```
## Not run:  
tm1_get_dimension_attributes(  
tm1_connection("localhost", "8881", "admin", "apple"),  
"region")  
  
con_obj <- tm1_connection("localhost", "8881", "admin", "apple")  
tm1_get_dimension_attributes(con_obj, "region")  
  
## End(Not run)
```

---

tm1\_get\_dimension\_elements

*TM1 Get Elements of a Dimension*

---

### **Description**

Gets elements of a dimension

### **Usage**

```
tm1_get_dimension_elements(tm1_connection, dimension)
```

### **Arguments**

tm1\_connection tm1 connection object returned by the function tm1\_connection  
dimension Name of a dimension as a string

**Examples**

```
## Not run:
tm1_get_dimension_elements(
tm1_connection("localhost", "8881", "admin", "apple"),
"region")

con_obj <- tm1_connection("localhost", "8881", "admin", "apple")
tm1_get_dimension_elements(con_obj, "region")

## End(Not run)
```

---

```
tm1_get_dimension_subsets
      TM1 Get Subsets of a Dimension
```

---

**Description**

Gets subsets of a dimension

**Usage**

```
tm1_get_dimension_subsets(tm1_connection, dimension)
```

**Arguments**

`tm1_connection` tm1 connection object returned by the function `tm1_connection`  
`dimension` Name of a dimension as a string

**Examples**

```
## Not run:
tm1_get_dimension_subsets(
tm1_connection("localhost", "8881", "admin", "apple"),
"region")

con_obj <- tm1_connection("localhost", "8881", "admin", "apple")
tm1_get_dimension_subsets(con_obj, "region")

## End(Not run)
```

---

tm1_get_element	<i>TM1 Get Element of a Dimension</i>
-----------------	---------------------------------------

---

**Description**

Gets element detail of a dimension. Name, UniqueName, Type, Level, Index, and Components. element or index should be specified

**Usage**

```
tm1_get_element(tm1_connection, dimension, element="", index = 0)
```

**Arguments**

tm1_connection	tm1 connection object returned by the function tm1_connection
dimension	Name of a dimension as a string
element	Name of element as a string
index	Index of element as a numeric

**Examples**

```
## Not run:
tm1_get_element(
tm1_connection("localhost", "8881", "admin", "apple"),
"month", "Year")

con_obj <- tm1_connection("localhost", "8881", "admin", "apple")
tm1_get_element(con_obj, "month", "", 7)

## End(Not run)
```

---

tm1_get_instances	<i>TM1 Get Instances</i>
-------------------	--------------------------

---

**Description**

Returns the list of tm1 instances in the specified adminhost

**Usage**

```
tm1_get_instances(adminhost = "localhost", port = "5898", ssl=TRUE)
```

**Arguments**

adminhost	adminhost of tm1 models
port	port of admin server
ssl	If TRUE it will be accesses through https



**Examples**

```
## Not run:
tm1_get_instances()

tm1_get_instances(adminhist = "localhost",
                  port = "5898", ssl = TRUE)

## End(Not run)
```

---

tm1_get_log	<i>TM1 Get Logs of an instance</i>
-------------	------------------------------------

---

**Description**

Gets server logs from a tm1 instance

**Usage**

```
tm1_get_log(tm1_connection, lognumber)
```

**Arguments**

tm1\_connection tm1 connection object returned by the function tm1\_connection  
lognumber Number of how many lines of logs you want. Default is 5

**Examples**

```
## Not run:
tm1_get_log(tm1_connection("localhost", "8881", "admin", "apple"), 10)

con_obj <- tm1_connection("localhost", "8881", "admin", "apple")
tm1_get_log(con_obj)

## End(Not run)
```

---

tm1_get_mdx_view	<i>TM1 Get Data from an MDX View</i>
------------------	--------------------------------------

---

**Description**

Gets mdx view data

**Usage**

```
tm1_get_mdx_view(tm1_connection, mdx, RowElementAsColumn = FALSE)
```

**Arguments**

tm1\_connection tm1 connection object returned by the function tm1\_connection  
 mdx MDX of view as a string  
 RowElementAsColumn  
                   if False, row elements will be attached to rownames of data frame

**Examples**

```
## Not run:
mdx <- "SELECT
  NON EMPTY
  {[month].[Jan],[month].[Feb],[month].[Mar]}
  ON COLUMNS,
  NON EMPTY
  {[account1].[Price],[account1].[Units]}
  ON ROWS
FROM [SalesCube]
WHERE
  (
    [actvsbud].[actvsbud].[Actual],
    [region].[region].[Argentina],
    [model].[model].[S Series 1.8 L Sedan]
  )"
tm1_get_mdx_view(
  tm1_connection("localhost", "8881", "admin", "apple"),
  mdx, RowElementAsColumn=FALSE)

con_obj <- tm1_connection("localhost", "8881", "admin", "apple")
tm1_get_mdx_view(con_obj,mdx)

## End(Not run)
```

---

tm1\_get\_native\_view     *TM1 Get Data from a Native View*

---

**Description**

Gets native view data

**Usage**

```
tm1_get_native_view(tm1_connection, cube, view, RowElementAsColumn= FALSE)
```

**Arguments**

tm1\_connection tm1 connection object returned by the function tm1\_connection  
 cube Name of the cube  
 view Name of the view  
 RowElementAsColumn  
                   if False, row elements will be attached to rownames of data frame

## Examples

```
## Not run:

tm1_get_native_view(
tm1_connection("localhost", "8881", "admin", "apple"),
  "SalesCube", "Default", RowElementAsColumn=FALSE)

con_obj <- tm1_connection("localhost", "8881", "admin", "apple")
tm1_get_native_view(con_obj, "SalesCube", "Default")

## End(Not run)
```

---

tm1\_get\_subset\_elements

*TM1 Get Elements of a subset*

---

## Description

Gets elements of a subset

## Usage

```
tm1_get_subset_elements(tm1_connection, dimension, subset)
```

## Arguments

tm1_connection	tm1 connection object returned by the function tm1_connection
dimension	Name of a dimension as a string
subset	Name of a subset as a string

## Examples

```
## Not run:
tm1_get_subset_elements(
tm1_connection("localhost", "8881", "admin", "apple"),
  "region", "default")

con_obj <- tm1_connection("localhost", "8881", "admin", "apple")
tm1_get_dimension_elements(con_obj, "region", "default")

## End(Not run)
```

---

`tm1_logout`*TM1 Log Out*

---

**Description**

Logs out

**Usage**

```
tm1_logout(tm1_connection)
```

**Arguments**

`tm1_connection` tm1 connection object returned by the function `tm1_connection`

**Examples**

```
## Not run:
tm1_logout(tm1_connection("localhost", "8881", "admin", "apple"))

con_obj <- tm1_connection("localhost", "8881", "admin", "apple")
tm1_logout(con_obj)

## End(Not run)
```

---

`tm1_run_chore`*TM1 Run a Chore*

---

**Description**

Runs a chore

**Usage**

```
tm1_run_chore(tm1_connection, chore)
```

**Arguments**

`tm1_connection` tm1 connection object returned by the function `tm1_connection`  
`chore` Name of a chore as a string

**Examples**

```
## Not run:
tm1_run_chore(tm1_connection("localhost", "8881", "admin", "apple"), "test")

con_obj <- tm1_connection("localhost", "8881", "admin", "apple")
tm1_run_chore(con_obj, "test")

## End(Not run)
```

---

tm1_run_process	<i>TM1 Run a Process</i>
-----------------	--------------------------

---

**Description**

Runs a process

**Usage**

```
tm1_run_process(tm1_connection,
  process,
  par1name, par1value,
  par2name, par2value,
  par3name, par3value)
```

**Arguments**

tm1_connection	tm1 connection object returned by the function tm1_connection
process	Name of a process as a string
par1name	Name of a parameter
par1value	Value of a parameter
par2name	Name of a parameter
par2value	Value of a parameter
par3name	Name of a parameter
par3value	Value of a parameter

**Examples**

```
## Not run:
tm1_run_process(tm1_connection("localhost", "8881", "admin", "apple"), "test")

con_obj <- tm1_connection("localhost", "8881", "admin", "apple")
tm1_run_process(con_obj, "test")

## End(Not run)
```

---

tm1\_send\_data

*TM1 Send Data to a Cube*


---

### Description

Send data to a cube, Supports up-to 10 dimension for now

### Usage

```
tm1_send_data(tm1_connection, value, cube,
              element1, element2, element3, element4, element5,
              element6, element7, element8, element9, element10,
              increment)
```

### Arguments

tm1_connection	tm1 connection object returned by the function tm1_connection
value	data value you want to send to cube
cube	Name of a cube as a string
element1	Element from 1st dimension of cube. Leave empty if there is no dimension
element2	Element from 2nd dimension of cube. Leave empty if there is no dimension
element3	Element from 3rd dimension of cube. Leave empty if there is no dimension
element4	Element from 4th dimension of cube. Leave empty if there is no dimension
element5	Element from 5th dimension of cube. Leave empty if there is no dimension
element6	Element from 6th dimension of cube. Leave empty if there is no dimension
element7	Element from 7th dimension of cube. Leave empty if there is no dimension
element8	Element from 8th dimension of cube. Leave empty if there is no dimension
element9	Element from 9th dimension of cube. Leave empty if there is no dimension
element10	Element from 10th dimension of cube. Leave empty if there is no dimension
increment	If TRUE, it will increment cube data by Value. If False, it will replace. This parameter is ignored in sending string values.

### Examples

```
## Not run:
tm1_send_data(
  tm1_connection("localhost", "8881", "admin", "apple"),
  10,
  "SalesCube",
  "Actual", "Argentina", "S Series 1.8 L Sedan", "Units", "Jan")

con_obj <- tm1_connection("localhost", "8881", "admin", "apple")
tm1_send_data(con_obj,
  10,
```

```

    "SalesCube",
    "Actual", "Argentina", "S Series 1.8 L Sedan", "Units", "Jan",
    increment=TRUE)

## End(Not run)

```

---

tm1_send_dataset	<i>TM1 Send Data Set to a Cube</i>
------------------	------------------------------------

---

## Description

Send data to a cube, Supports up-to 10 dimension for now

## Usage

```

tm1_send_dataset(tm1_connection, valueset, cube, rowdim, coldim,
                rowdim2, rowdim3, rowdim4, rowdim5,
                titledim1, titleel1, titledim2, titleel2,
                titledim3, titleel3, titledim4, titleel4,
                titledim5, titleel5, titledim6, titleel6,
                titledim7, titleel7, titledim8, titleel8)

```

## Arguments

tm1_connection	tm1 connection object returned by the function tm1_connection
valueset	data frame or matrix object holding values you want to send to cube
cube	Name of a cube as a string
rowdim	Corresponding dimension of the elements on row
coldim	Corresponding dimension of the elements on column
rowdim2	Corresponding dimension of the elements on row2
rowdim3	Corresponding dimension of the elements on row3
rowdim4	Corresponding dimension of the elements on row4
rowdim5	Corresponding dimension of the elements on row5
titledim1	Name of dimension in title
titleel1	Element of dimension in corresponding titledim
titledim2	Name of dimension in title
titleel2	Element of dimension in corresponding titledim
titledim3	Name of dimension in title
titleel3	Element of dimension in corresponding titledim
titledim4	Name of dimension in title
titleel4	Element of dimension in corresponding titledim
titledim5	Name of dimension in title

titleel5	Element of dimension in corresponding titledim
titledim6	Name of dimension in title
titleel6	Element of dimension in corresponding titledim
titledim7	Name of dimension in title
titleel7	Element of dimension in corresponding titledim
titledim8	Name of dimension in title
titleel8	Element of dimension in corresponding titledim

### Examples

```
## Not run:

sdata <- tm1_connection("localhost", "8881", "admin", "apple")

#valueset
#   Argentina Brazil
#Jan      1      2
#Feb      3      4

tm1_send_dataset(
  sdata,
  valueset = valueset, cube = "SalesCube",
  rowdim = "month", coldim = "region",
  titledim1 = "actvsbud", titleel1 = "Actual",
  titledim2 = "model", titleel2 = "L Series 1.6 L Convertible",
  titledim3 = "account1", titleel3 = "Units")

## End(Not run)
```



# Index

tm1\_api\_request, [2](#)  
tm1\_connection, [3](#)  
tm1\_create\_element, [4](#)  
tm1\_create\_mdx, [4](#)  
tm1\_create\_subset, [7](#)  
tm1\_create\_view, [7](#)  
tm1\_delete\_element, [8](#)  
tm1\_delete\_subset, [9](#)  
tm1\_delete\_view, [10](#)  
tm1\_get\_config, [10](#)  
tm1\_get\_cube\_dimensions, [11](#)  
tm1\_get\_cubes, [11](#)  
tm1\_get\_data, [12](#)  
tm1\_get\_dimension\_attributes, [14](#)  
tm1\_get\_dimension\_elements, [14](#)  
tm1\_get\_dimension\_subsets, [15](#)  
tm1\_get\_dimensions, [13](#)  
tm1\_get\_element, [16](#)  
tm1\_get\_instances, [16](#)  
tm1\_get\_log, [17](#)  
tm1\_get\_mdx\_view, [17](#)  
tm1\_get\_native\_view, [18](#)  
tm1\_get\_subset\_elements, [19](#)  
tm1\_logout, [20](#)  
tm1\_run\_chore, [20](#)  
tm1\_run\_process, [21](#)  
tm1\_send\_data, [22](#)  
tm1\_send\_dataset, [23](#)